
OM11UP: Upgrade Instructions for OM1106 Software HASP Key

Thank you for your purchase of an OM11UP upgrade for your OM1106 software product. Use the following instructions to update your OM1106 USB HASP key to enable purchased upgrade functions:

1. Copy the emailed zipped folder onto a PC.
2. Unzip the folder.
3. Insert the OM1106 HASP key into a USB port on the PC with the unzipped file.
4. Open a web browser and type the following in the web browser address field: **http://localhost:1947**. This opens the **Safenet Sentinel Admin Control Center** application.
5. Click **Options > Update/Attach**.
6. Click **Browse** and navigate to and select the unzipped file with the extension **v2c**.
7. Click **Apply File**. Wait for the program to complete the HASP key update.
8. Click **Options > Features** in left column and check that the ordered feature has been enabled for the product (for example, **14** for QAM or **16** for MCS) .
9. Remove the OM1106 HASP key. The upgraded key is ready to use on the PC with the OM1106 software.

