
Tektronix[®]

TekVISA Programmer Manual



077-0140-02

Tektronix[®]

TekVISA Programmer Manual

Register now! Click the following link to protect your product. tek.com/register

077-0140-02 December 2023

Copyright © 2023, Tektronix. 2023 All rights reserved. Licensed software products are owned by Tektronix or its subsidiaries or suppliers, and are protected by national copyright laws and international treaty provisions. Tektronix products are covered by U.S. and foreign patents, issued and pending. Information in this publication supersedes that in all previously published material. Specifications and price change privileges reserved. All other trade names referenced are the service marks, trademarks, or registered trademarks of their respective companies.

TEKTRONIX and TEK are registered trademarks of Tektronix, Inc.

Tektronix, Inc. 14150 SW Karl Braun Drive P.O. Box 500 Beaverton, OR 97077 US

For product information, sales, service, and technical support visit *tek.com* to find contacts in your area. For warranty information visit *tek.com/warranty*.

Contents

Preface	9
Who should read this manual	9
About this manual	9
Conventions	9
Related manuals and information	10
Getting started	11
Product description	11
Terminology	
What you need to get started	15
TekVISA installation	15
Operations summary	17
Operations	
viAssertTrigger (vi, protocol)	19
viBufRead (vi, buf, count, retCount)	
viBufWrite (vi, buf, count, retCount)	
viClear (vi)	24
viClose (vi)	
viDisableEvent (vi, eventType, mechanism)	
viDiscardEvents (vi, eventType, mechanism)	
viEnableEvent (vi, eventType, mechanism, context)	30
viEventHandler (vi, eventType, context, userHandle)	
viFindNext (findList, instrDesc)	
viFindRsrc (sesn, expr, findList, retCount, instrDesc)	
viFlush (vi, mask)	
viGetAttribute (vi, attribute, attrState)	41
viGpibCommand (vi, buf, count, retCount)	
vilnstallHandler (vi, eventType, handler, userHandle)	
viLock (vi, lockType, timeout, requestedKey, accessKey)	
viOpen (sesn, rsrcName, accessMode, timeout, vi)	
viOpenDefaultRM (sesn)	
viParseRsrc (sesn, rsrcName, intfType, intfNum)	
viParseRsrcEx (sesn, rsrcName, intfType, intfNum, rsrcClass, unaliasedExpandedRsrcName, aliasIfExists)	
viPrintf (vi, writeFmt, <arg1, arg2,="">)</arg1,>	
viQueryf (vi, writeFmt, readFmt, <arg1, arg2,="">)</arg1,>	60
viRead (vi, buf, count, retCount)	
viReadAsync (vi, buf, count, jobId)	
viReadSTB (vi, status)	
viReadToFile (vi, fileName, count, retCount)	
viScanf (vi, readFmt, <arg1, arg2,="">)</arg1,>	
viSetAttribute (vi, attribute, attrState)	
viSetBuf (vi, mask, size)	
viSPrintf (vi, buf, writeFmt, <arg1, arg2,="">)</arg1,>	
viSScanf (vi, buf, readFmt, <arg1, arg2,="">)</arg1,>	
viStatusDesc (vi, status, desc)	83

viTerminate (vi, degree, jobld)	84
viUninstallHandler (vi, eventType, handler, userHandle)	
viUnlock (vi)	
viUsbControlln (vi, bmRequestType, bRequest, wValue, wIndex, wLength, buffer, retCount)	
viUsbControlOut (vi, bmRequestType, bRequest, wValue, wIndex, wLength, buffer)	
viVPrintf (vi, writeFmt, params)	
viVQueryf (vi, writeFmt, readFmt, params)	
viVScanf (vi, readFmt, params)	
viVSPrintf (vi, buf, writeFmt, params)	
viVSScanf (vi, buf, readFmt, params)	
viWaitOnEvent (vi, inEventType, timeout, outEventType, outContext)	
viWrite(vi, buf, count, retCount)	
viWriteAsync (vi, buf, count, jobld)	
viWriteFromFile (vi, fileName, count, retCount)	
viPxiReserveTriggers(vi, cnt, trigBuses, trigLines, failureIndex)	
Attributes summary	
Attributes	
VI_ATTR_ASRL_AVAIL_NUM	
VI_ATTR_ASRL_BAUD	116
VI_ATTR_ASRL_CTS_STATE	116
VI_ATTR_ASRL_DATA_BITS	117
VI_ATTR_ASRL_DCD_STATE	
VI_ATTR_ASRL_DSR_STATE	
VI_ATTR_ASRL_DTR_STATE	
VI_ATTR_ASRL_END_IN	119
VI_ATTR_ASRL_END_OUT	119
VI_ATTR_ASRL_FLOW_CNTRL	
VI_ATTR_ASRL_PARITY	
VI_ATTR_ASRL_REPLACE_CHAR	
VI_ATTR_ASRL_RI_STATE	
VI_ATTR_ASRL_RTS_STATE	
VI_ATTR_ASRL_STOP_BITS	
VI_ATTR_ASRL_XOFF_CHAR	
VI_ATTR_ASRL_XON_CHAR	
VI_ATTR_EVENT_TYPE	
VI_ATTR_GPIB_PRIMARY_ADDR	
VI_ATTR_GPIB_READDR_EN	
VI_ATTR_GPIB_SECONDARY_ADDR	
VI_ATTR_GPIB_UNADDR_EN	
VI_ATTR_INTF_INST_NAME	
VI_ATTR_INTF_NUM	
VI_ATTR_INTF_TYPE	
VI_ATTR_IO_PROT	
VI_ATTR_MAX_QUEUE_LENGTH	
VI_ATTR_OPER_NAME	
VI_ATTR_RD_BUF_OPER_MODE	
VI_ATTR_RET_COUNT	130

VI_ATTR_RM_SESSION	
VI_ATTR_RSRC_IMPL_VERSION	
VI_ATTR_RSRC_LOCK_STATE	
VI_ATTR_RSRC_MANF_ID	
VI_ATTR_RSRC_MANF_NAME	
VI ATTR RSRC NAME	
VI ATTR RSRC SPEC VERSION	
VI_ATTR_SEND_END_EN	
VI_ATTR_STATUS	
VI_ATTR_SUPPRESS_END_EN	
VI_ATTR_TCPIP_ADDR	
VI_ATTR_TCPIP_HISLIP_MAX_MESSAGE_KB	
VI_ATTR_TCPIP_HISLIP_OVERLAP_EN	
VI_ATTR_TCPIP_HISLIP_VERSION	
VI_ATTR_TCPIP_HOSTNAME	
VI_ATTR_TCPIP_IS_HISLIP	
VI_ATTR_TCPIP_KEEPALIVE	
VI_ATTR_TCPIP_NODELAY	
VI_ATTR_TCPIP_PORT	
VI_ATTR_TERMCHAR	
VI_ATTR_TERMCHAR_EN	
VI_ATTR_TMO_VALUE	140
VI_ATTR_TRIG_ID	
VI_ATTR_TCPIP_IS_HISLIP	141
VI_ATTR_USB_INTFC_NUM	
VI_ATTR_USB_MAX_INTR_SIZE	
VI_ATTR_USB_PROTOCOL	
VI_ATTR_USB_RECV_INTR_DATA	
VI_ATTR_USB_RECV_INTR_SIZE	
VI_ATTR_USB_SERIAL_NUM	
VI_ATTR_USER_DATA	
VI_ATTR_WR_BUF_OPER_MODE	
Events	
VI_EVENT_EXCEPTION	
VI_EVENT_SERVICE_REQ	
Programming examples	
Introduction	
Compiling and linking examples	
Opening and closing sessions	
SIMPLE.CPP example	
Finding resources.	
SIMPLEFINDRSRC.CPP example	
FINDRSRCATTRMATCH.CPP example	
Setting and retrieving attributes	
ATTRACCESS.CPP example	
Basic Input/Output	
Reading and Writing Data	

Synchronous Read/Write	
Extract from SIMPLE.CPP Example	
RWEXAM.CPP Example	155
Asynchronous Read/Write	156
Status/Service request	157
Reading and writing formatted data	
FORMATIO.CPP example	158
Resizing the formatted I/O buffers	
BUFFERIO.CPP Example	
Flushing the formatted I/O buffer	
Buffered I/O operations	
Variable list operations	164
Controlling the serial I/O buffers	164
Handling events	165
SRQWAIT.CPP example	165
Callback mechanism.	
SRQ.CPP example	
Exception handling	170
Generating an Error condition on asynchronous operations	171
Locking and unlocking resources	
Locking types and access privileges	
EXLOCKEXAM.CPP example	172
Testing exclusive locking	173
Lock sharing	173
Acquiring an exclusive lock while owning a shared lock	174
Nested locks	174
SHAREDLOCK.CPP example	
Testing shared locking	176
Building a graphical user interface	
Appendix A: VISA data type assignments	179
Appendix B: Completion and error codes	
Glossary	

Preface

Who should read this manual

This manual is used for both reference and tutorial purpose. It is intended for use by Tektronix instrumentation end users and application programmers who wish to develop or modify:

- · VISA-compliant instrument driver software.
- · Applications that use VISA-compliant instrument driver software.

About this manual

This programming manual describes TekVISA, the Tektronix implementation of the Virtual Instrument Software Architecture (VISA) Library, an interface-independent software interface endorsed by the VXIplug&play Systems Alliance. The manual is organized as follows:

- The Preface and Getting Started sections briefly cover the audience and conventions for this guide, present overview concepts, summarize TekVISA features and applications, and explain how to configure TekVISA resources.
- The Reference section presents TekVISA operations, attributes, and events in alphabetical order.
 - The Operations Summary chapter summarizes the VISA operations implemented by Tektronix.
 - The Operations chapter describes each VISA operation including its syntax and sample usage.
 - The Attributes Summary chapter summarizes the VISA attributes implemented by Tektronix.
 - · The Attributes chapter describes each VISA attribute including its syntax and usage.
 - The Events chapter describes each VISA event implemented by Tektronix including its syntax and usage.
- The Programming Examples section contains short programs that illustrate usage of VISA operations, attributes, and events to
 accomplish specific tasks.
- · Appendices contain summary information for quick reference.
 - The VISA Data Type Assignments appendix lists VISA data types in alphabetical order.
 - The Completion and Error Codes appendix lists operation completion codes and error codes in alphabetical order.
- · A Glossary and Index appear at the end of the manual.

Conventions

This manual makes use of certain notational conventions and typefaces in distinctive ways, as summarized in Table i.

Table 1: Typographic conventions

Typeface	Meaning	Example
italics	Used to introduce terms or to specify variables for which actual values should be substituted.	A common I/O library called the Virtual Instrument Software Architecture (VISA)
		The <i>requestedKey</i> will be copied into the user buffer referred to by the <i>access Key</i> .
boldface	Used to emphasize important points or to denote exact characters to type or buttons to click in step-by-step procedures.	The viFindRsrc() operation matches an expression against the resources available for a particular interface.
		Click OK .

Table continued...

Typeface	Meaning	Example
NOTE	Used to call attention to notes or tips in text.	Note: Read this carefully
<item1, item2,=""></item1,>	This notation is used to designate a variable list of one or more items separated by commas.	<pre>viScanf (vi, readFmt, <arg1, arg2,>)</arg1, </pre>
Code	This font is used to designate blocks of code.	<pre>*result = m_ViStatus;</pre>
Menu > Submenu	This notation is used to designate a series of cascading menus.	Choose File > Open.
	The example here means: from the File menu, choose Open.	

Related manuals and information

Refer to the following manuals for information regarding related products, manuals, and programming specifications.

- This programming manual resides in Adobe Acrobat format on the TekVISA Product Software CD.
- The AD007 GPIB-LAN Adapter User Manual (071-0245-XX) provides related information if you are controlling your instrumentation from a remote PC over an Ethernet GPIB-LAN connection. This guide is located on the AD007 Product Software CD.
- · Refer to the Online Help and Programmer Online Guide for information to use and program each instrument.
- General information and specifications for Virtual Instrument Software Architecture (VISA) are available from the web site of the VXIplug&play System Alliance at *ivifoundation.org/specifications/default.aspx*. The following document relates to the Tektronix implementation of VISA:



Note: Some of the latest VISA specifications are now available at the IVI Foundation web site at www.ivifoundation.org.

- VPP-4.3: The VISA Library Revision 3.0. This specification is intended to be used in conjunction with the VPP-3.X specifications supporting instrument driver development.
- VPP-4.3.5: VISA Shared Components.
- All related specifications for the VXIplug&play are available at ivifoundation.org/specifications/default.aspx .
- All related specifications for the IVI are available at www.ivifoundation.org.

Getting started

Product description

Test and measurement applications require some kind of I/O library to communicate with test instrumentation. As a step toward industry-wide software compatibility, the VXIplug&play Systems Alliance developed a common I/O library called the Virtual Instrument Software Architecture (VISA). It provides a common standard for software developers so that software from multiple vendors, such as instrument drivers, can run on the same platform.

An instrument driver is a library of functions that handles the details of controlling and communicating with a specific instrument such as a Tektronix oscilloscope. Instrumentation end users have been writing their own instrument drivers for years.

This manual describes TekVISA, the Tektronix implementation of the VISA Application Programming Interface (API). TekVISA is industrycompliant software, available with selected Tektronix instrument models, for writing interoperable instrument drivers in a variety of Application Development Environments (ADEs).

TekVISA implements a subset of Version 3.0 of the VISA specification for controlling GPIB, USB, and serial (RS-232) instrument interfaces locally or remotely via an Ethernet LAN connection. TekVISA provides the interface-independent functionality needed to control and access the embedded software of Tektronix test and measurement equipment in the following ways:

• Using :

- · Virtual GPIB software running locally on Windows-based instrumentsation
- Physical GPIB controller hardware
- Asynchronous serial controller hardware
- · USB connection for USB instruments such as the TDS1000B and TDS2000B series
- · TekLink hardware to TekLink-enabled instruments
- Supports 32-bit and 64-bit VISA Shared Components. The standard directory structure, environment variables, and registry entries are per VISA Shared Components version 1.1.0.
- Over a Local Area Network (LAN) that uses VXI-11 protocol, TCP/IP Socket, and one of the following:
 - · An AD007 LAN-to-GPIB adapter to GPIB controller hardware
 - An Ethernet connection together with VXI-11 server running on Windows-based instruments such as the TDS7000 and TDS/ CSA8000 Series Oscilloscopes
 - An Ethernet connection together with Socket server running on Windows-based instruments such as the DPO/DSA7000 Series
 Oscilloscopes.

Features and benefits


TekVISA offers the following features and benefits:

- · Improves ease of use for end users by providing a consistent methodology for using instrument drivers from a variety of vendors
- Provides language interface libraries for programmers using multiple Application Development Environments as shown in Figure 1-1, including:
 - Microsoft C/C++
 - \u0002 Microsoft Visual Basic
 - \u0002 LabVIEW graphics software using the G language
 - \u0002 MATLAB analysis software
- · Provides an Instrument Manager utility for setting up and searching additional VISA resources
- · Provides debugging utilities such as TalkerListener and CallMonitor
- Allows software installation on any number of PCs

Applications and connectivity supportedby TekVISA

TekVISA is beneficial in a variety of situations and applications:

- A single instrument driver can be used by multiple Application Development Environments.
- · Instrument drivers from several vendors can be combined in a single user application.
- User programs running on Windows-based instrumentation can use TekVISA to control instrument operation via a virtual GPIB software connection, without using any external GPIB hardware.
- User programs running on remote PCs networked toWindows-based instrumentation can use TekVISA to control instrument operation via a virtual GPIB, VXI-11 server, and Socket server connection. No external GPIB-LAN hardware is needed. Only an Ethernet LAN connection is required.
- User programs connected locally or remotely to other non-Windows-based Tektronix instrumentation can use TekVISA to control instrument operation via a GPIB, USB, or serial (RS232) connection locally, or remotely via TCPIP directly or via a Tektronix AD007 GPIB-LAN adapter.



Application Development Environments (ADE)

Figure 1: TekVISA Supports Multiple Development Environments




Figure 2: TekVISA supports local and remote connectivity

Terminology

The VISA specification introduces a number of new terms. Refer to the Glossary at the end of this manual for a complete list of terms and definitions. Some key terms are discussed in the following paragraphs and illustrated in *Figure 3* on page 14.

Resources, INSTR resource, SOCKET resource, and sessions

VISA defines an architecture consisting of many resources that encapsulate device functionality. In VISA, every defined software module is a resource. In general, the term resource is synonymous with the word object in object-oriented architectures. For VISA, resource more specifically refers to a particular implementation or instance, in object-oriented terms, of a resource class, which is the definition for how to create a particular resource.

A specialized type of resource class is a VISA instrument control (INSTR) resource class, which defines how to control a particular device. An INSTR resource class encapsulates the various operations for a particular device together (reading, writing, triggering, and so on) so that a program can interact with that device through a single resource. TekVISA supports many kinds of devices associated with the INSTR resource class: GPIB, ASRL (serial) devices, USB, TCPIP/LAN, and TekLink.

The TCP/IP Socket (SOCKET) Resource encapsulates the operations and properties of the capabilities of a raw network socket connection using TCP/IP. A VISA Socket Resource like the INSTR resource, starts with the basic operations and attributes of the VISA Resource Template. The SOCKET Resource exposes the capability of a raw network socket connection over TCP/IP

Applications that use VISA can access device resources by opening sessions to them. A session is a communication path between a software element and aresource. Every session in VISA is unique and has its own life cycle. VISAdefines a locking mechanism to restrict access to resources for special circumstances.

Operations, Attributes, and Events

After establishing a session, an application can communicate with a resource by invoking operations associated with the resource or by updating characteristics of resources called attributes. Some attributes depict the instantaneous state of the resource and others define changeable parameters that modify the behavior of resources. A VISA system also allows information exchange through events.

The Resource manager

VISA Resource Manager is the name given to the part of VISA that manages resources. This management includes support for opening, closing, and finding resources; setting and retrieving resource attributes; generating events on resources; and so on.

The VISA Resource Manager provides access to all resources registered with it. It is therefore at the root of a subsystem of connected resources. Currently, one Resource Manager is available by default after initialization. This is called the Default Resource Manager. This identifier is used when opening resources, finding available resources, and performing other operations on device resources.




Figure 3: Key VISA teriminology for INSTR resourse




Figure 4: Key VISA Terminology for SOCKET Resource

Note: SOCKET connections do not support VISA Events. SOCKET connections automatically perform a viLock() of the interface and cannot be shared like other VISA bus types.

Virtual instruments and virtual GPIB

A virtual instrument is a name given to the grouping of software modules (VISA resources with any associated or required hardware) to give the functionality of a traditional stand-alone instrument. Within VISA, a virtual instrument is the logical grouping of any of the VISA resources. TekVISA supports USB, ASRL (serial) and GPIB virtual instruments, which work with accompanying USBTMC, RS-232 and GPIB hardware respectively.

In addition, TekVISA includes a specialized type of GPIB resource called virtual GPIB. User programs running on oscilloscopes with Windows-based instrumentation, or running on a remote PC connected by LAN to such an instrument, can access the embedded instrument software by using a virtual GPIB software connection, without the need for any GPIB controller hardware or cables.

What you need to get started

TekVISA installation

The software installation includes a utility to help you configure TekVISA resources. The VISA Instrument Manager allows you to detect USB, GPIB, and serial (ASRL) resource assignments, and to add or remove remote hosts (such as VXI-11 or Socket clients connected by Ethernet LAN or by an AD007 adapter and associated GPIB hardware).



Note: If you are connecting to a network just to print screen hardcopy data, you do not need to install or configure TekVISA software.

TekVISA comes installed on current Tektronix MS-Windows oscilloscopes as part of the Product Software.

To install TekVISA software on a PC connected to your Tektronix oscilloscope, follow the steps shown below on Table .

Table 2: Installing TekVISA Software on a PC

Alternative Locations for Finding TekVISA Software	Instructions for Installing TekVISA Software on a PC
	In your MS-Windows computer, select Start > Run , browse the CD to the TekVISA folder, and run setup.exe.

Table continued...

<u>/</u>!

Alternative Locations for Finding TekVISA Software	Instructions for Installing TekVISA Software on a PC
The TDSPCS1 OpenChoice PC Communications Software CD	Follow the instructions in the installation wizard.
The OpenChoice Solutions Software Developers' Kit CD	Click on the Developers' Kit browser button for Software Drivers and then for TekVISA
The current TekVISA installation download from the Tektronix Web site	Unzip the downloaded file in a temporary directory of your choice and run setup.exe.
	The IVI foundation VISA shared components will get installed as part of the TekVISA installation

Note: If you have already installed TekVISA from an earlier version of the Tektronix Software Solutions CD or with Wavestar, you should uninstall that version first, and then reinstall TekVISA from the most recent source.

The TekVISA Configuration Utility

Included with the TekVISA installation is the TekVISA Instrument Manager utility, which lets you find resource assignments and add or remove network hosts (instruments). Once an instrument is added to the TekVISA configuration, you can communicate with it by using a VISA compliant instrument driver.

To run the TekVISA Instrument Manager utility, you click on the TekVISA resource maanger icon in the system tray shown in *Figure* 4 on page 15. Alternatively, you can select, **Start > Programs > TekVISA > OpenChoice Instrument Manager**.



Figure 5: System tray

Operations summary

The following table summarizes Tektronix VISA operations by category.

Table 3: Table of VISA operations by category

Operation	Description	
Opening and closing sessions, Events, an	d Find lists	
viOpenDefaultRM	Return a session to the Default Resource Manager	
viOpen	Open a session to the specified resource	
viClose	Close the specified session, event, or find list	
Finding resources		
viFindRsrc	Find a list of resources associated with a specified interface	
viFindNext	Return the next resource from the find list	
viParseRsrc	Parses a resource string to get the interface information	
Setting and retrieving attributes		
viGetAttribute	Retrieve the state of an attribute for the specified session, event, or find list	
viSetAttribute	Set the state of an attribute for the specified session, event, or find list	
viStatusDesc	Retrieve a user-readable description of the specified status code	
Reading and writing basic data		
viWrite	Write data synchronously to a device from the specified buffer	
viWriteAsync	Write data asynchronously to a device from the specified buffer	
viWriteFromFile	Take data from a file and write it to a device synchronously	
viRead	Read data synchronously from a device into the specified buffer	
viReadAsync	Read data asynchronously from a device into the specified buffer	
viReadToFile	Read data synchronously from a device and store the transferred data in a file	
viTerminate	Terminate normal execution of an asynchronous read or write operation	
Other basic I/O operations		
viClear	Clear a device	
viAssertTrigger	Assert software or hardware trigger	
viReadSTB	Read a status byte of the service request	
Reading and writing formatted data		
Formatted Buffer Operations		
viBufWrite	Write data synchronously to a device from the formatted I/O buffer	
viBufRead	Read data synchronously from a device into the formatted I/O buffer	
viSetBuf	Set the size of the formatted I/O and/or serial buffer(s)	
viFlush	Manually flush the specified buffer(s)	
Formatted Write Operations * (See Note)		
viPrintf	Format and write data to a device using a variable argument list	
viVprintf	Format and write data to a device using a pointer to a variable argument list	
Table continued		

Operation	Description
viSPrintf	Format and write data to a user-specified buffer using a variable argument list
viVSPrintf	Format and write data to a user-specified buffer using a pointer to a variable argument list
Formatted Read Operations * (See	Note)
viScanf	Read and format data from a device using a variable argument list
viVScanf	Read and format data from a device using a pointer to a variable argument list
viSScanf	Read and format data from a user-specified buffer using a variable argument list
viVSScanf	Read and format data from a user-specified buffer using a pointer to a variable argument list
Formatted Read/Write Operations *	(See Note)
viQueryf	Write and read formatted data to and from a device using a variable argument list
viVQueryf	Write and read formatted data to and from a device using a pointer to a variable argument list
Handling events	
viEnableEvent	Enable notification of a specified event
viDisableEvent	Disable notification of the specified event using the specified mechanism
viDiscardEvents	Discard all pending occurrences of the specified events for the specified mechanism(s) and session
viWaitOnEvent	Wait for an occurrence of the specified event for a given session
vilnstallHandler	Install callback handler(s) for the specified event
viUninstallHandler	Uninstall callback handler(s) for the specified event
viEventHandler	Prototype for handler(s) to be called back when a particular event occurs
Locking and unlocking resource	5
viLock	Obtain a lock on the specified resource
viUnlock	Relinquish a lock on the specified resource
Operations specific to interface t	уре
viUsbControlIn	Request arbitrary data from a USB device on the default control port
viUsbControlOut	Send arbitrary data to a USB device on the default control port

Operations

The following Tektronix VISA operations are presented in alphabetical order.

viAssertTrigger (vi, protocol)

Usage

Asserts a software trigger for a GPIB, USBTMC, or serial device.

C Format

```
ViStatus viAssertTrigger (ViSession vi, ViUInt16 protocol)
```

Visual basic format

```
viAssertTrigger (ByVal vi As Long, ByVal protocol As Integer) As Long
```

Parameters

Table 4: viAssertTrigger() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
protocol		Trigger protocol to use during assertion. Valid values are: VI_TRIG_PROT_DEFAULT

Return values

Table 5: viAssertTrigger() Completion codes

Completion codes	Description
VI_SUCCESS	The specified trigger was successfully asserted to the device.

Table 6: viAssertTrigger() Error codes

Error Codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_NSUP_OPER	The given vi does not support this operation.
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_INV_PROT	The protocol specified is invalid.
VI_ERROR_TMO	Timeout expired before operation completed.
VI_ERROR_RAW_WR_PROT_VIOL	Violation of raw write protocol occurred during transfer.
VI_ERROR_RAW_RD_PROT_VIOL	Violation of raw read protocol occurred during transfer.
VI_ERROR_INP_PROT_VIOL	Device reported an input protocol error during transfer.
Table continued	

TekVISA Programmer Manual

Error Codes	Description	
VI_ERROR_BERRt	Bus error occurred during transfer.	
VI_ERROR_LINE_IN_USE	The specified trigger line is currently in use.	
VI_ERROR_NCIC	The interface associated with the given vi is not currently the controller in charge.	
VI_ERROR_NLISTENERS	No Listeners condition is detected (both NRFD and NDAC are deasserted).	
VI_ERROR_INV_SETUP	Unable to start operation because setup is invalid (due to attributes being set to an inconsistent state).	

C example

```
ViSession rm, vi;
ViUInt16 val;
if (viOpenDefault(&rm) < VI_SUCCESS) return;
if (viOpen(rm, "GPIB8::1::INSTR", VI_NULL, VI_NULL, &vi)
< VI_SUCCESS) return;
viAssertTrigger(vi, value);
viClose(rm);
```

Comments

The viAssertTrigger() operation will assert a software trigger as follows:

- · For a GPIB device, the device is addressed to listen, and then the GPIB GET command is sent.
- For a serial device, if VI_ATTR_IO_PROT is VI_ASRL488, the device is sent the string "*TRG\n". This operation is not valid for a serial device if VI_ATTR_IO_PROT is VI_NORMAL.
- For GPIB, USBTMC, and serial software triggers, VI_TRIG_PROT_DEFAULT is the only valid protocol.

See also

Basic Input/Output VI_ATTR_IO_PROT

viBufRead (vi, buf, count, retCount)

Usage

Writes data synchronously to a device from the formatted I/O buffer.

C format

ViStatus viBufWrite(ViSession vi, ViBuf buf, ViUInt32 count, ViPUInt32 retCount)

Visual basic format

viBufWrite(ByVal vi As Long, ByVal buf As String, ByVal count As Long, retCount As Long) As Long

Parameters

Table 7: viBufWrite() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
buf	OUT	Represents the location of a data block to be sent to the device.
count	IN	Number of bytes to be written.
retCount		Represents the location of an integer that will be set to the number of bytes actually transferred.

Return values

Table 8: viBufWrite() completion codes

Completion codes	Description
VI_SUCCESS	Operation completed successfully.

Table 9: viBufWrite() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_NSUP_OPER	The given vi does not support this operation.
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_TMO	Timeout expired before operation completed.
	If this operation returns this message, the write buffer for the specified session is cleared.
VI_ERROR_INV_SETUP	Unable to start write operation because setup is invalid (due to attributes being set to an inconsistent state).
VI_ERROR_IO	An unknown I/O error occurred during transfer.

C example

ViSession rm, vi; char buffer[256]; if (viOpenDefault(&rm) < VI_SUCCESS) return; if (viOpen(rm, "GPIB8::1::INSTR", VI_NULL, VI_NULL, &vi) < VI_SUCCESS) return; if (viBufWrite(vi, (ViBuf) "*IDN?", 5, VI_NULL) < VI_SUCCESS) return; viBufRead(vi, (ViBuf) buffer, sizeof(buffer), VI_NULL); printf("%s\n", buffer); viClose(rm);

Comments

The viBufWrite() operation is similar to viWrite() and does not perform any kind of data formatting. It differs from viWrite() in that the data is written to the formatted I/O write buffer—the same buffer used by viPrintf() and related operations—rather than directly to the device.



Note: You can intermix this operation with viPrintf() but you should not mix it with viWrite().

Table 10: Special value for retCount parameter with viBufWrite()

Value	Description
	If you pass this value, the number of bytes transferred is not returned. You may find this useful if you only need to know whether the operation succeeded or failed.

See also

Reading and Writing formatted data viBufWrite (vi, buf, count, retCount)

viBufWrite (vi, buf, count, retCount)

Usage

Writes data synchronously to a device from the formatted I/O buffer.

C format

```
ViStatus viBufWrite(ViSession vi, ViConstBuf buf, ViUInt32 count, ViPUInt32 retCount)
```

Visual basic format

```
viBufWrite(ByVal vi As Long, ByVal buf As String, ByVal count As Long, retCount As Long) As Long
```

Parameters

Table 11: viBufWrite() Parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
buf	OUT	Represents the location of a data block to be sent to device.
count	IN	Number of bytes to be written.
retCount		Represents the location of an integer that will be set to the number of bytes actually transferred.

Return values

Table 12: viBufWrite() Completion codes

Completion codes	Description
VI_SUCCESS	Operation completed successfully.

Table 13: viBufWrite() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_NSUP_OPER	The given vi does not support this operation.
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_TMO	Timeout expired before operation completed.
	If this operation returns this message, the write buffer for the specified session is cleared.
VI_ERROR_INV_SETUP	Unable to start write operation because setup is invalid (due to attributes being set to an inconsistent state).
VI_ERROR_IO	An unknown I/O error occurred during transfer.

C example

ViSession rm, vi; char buffer[256]; if (viOpenDefault(&rm) < VI_SUCCESS) return; if (viOpen(rm, "GPIB8::1::INSTR", VI_NULL, VI_NULL, &vi) < VI_SUCCESS) return; **if (viBufWrite(vi, (ViBuf) "*IDN?", 5, VI_NULL) < VI_SUCCESS) return;** viBufRead(vi, (ViBuf) buffer, sizeof(buffer), VI_NULL); printf("%s\n", buffer); viClose(rm);

Comments

The viBufWrite() operation is similar to viWrite() and does not perform any kind of data formatting. It differs from viWrite() in that the data is written to the formatted I/O write buffer—the same buffer used by viPrintf() and related operations—rather than directly to the device.



Note: You can intermix this operation with viPrintf(), but you should not mix it with viWrite().

Table 14: Special Value for retCount Parameter with viBufWrite()

Value	Description
_	If you pass this value, the number of bytes transferred is not returned. You may find this useful if you only need to know whether the operation succeeded or failed.

See also

Reading and writing formatted data

viClear (vi)

Usage

Clears a device.

C Format

ViStatus viClear (ViSession vi)

Visual basic format

viClear (ByVal vi As Long) As Long

Parameters

Table 15: viClear() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.

Return values

Table 16: viClear() completion codes

Completion codes	Description
VI_SUCCESS	Operation completed successfully.

Table 17: viClear() error codes

Error Codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_NSUP_OPER	The given vi does not support this operation.
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_TMO	Timeout expired before operation completed.
VI_ERROR_RAW_WR_PROT	Violation of raw read protocol occurred during transfer.
_VIOL	
VI_ERROR_RAW_RD_PROT	Violation of raw read protocol occurred during transfer.
_VIOL	
VI_ERROR_BERRt	Bus error occurred during transfer.
VI_ERROR_NCIC	The interface associated with the given vi is not currently the controller in charge.
VI_ERROR_NLISTENERS	No Listeners condition is detected (both NRFD and NDAC are deasserted).
VI_ERROR_INV_SETUP	Unable to start operation because setup is invalid (due to attributes being set to an inconsistent state).

C Example

```
ViSession rm, vi;
if (viOpenDefault(&rm) < VI_SUCCESS) return;
if (viOpen(rm, "GPIB8::1::INSTR", VI_NULL, VI_NULL, &vi)
< VI_SUCCESS) return;
viClear(vi);
viClose(rm);
```

Comments

The viClear() operation performs an IEEE 488.1-style clear of the device.

- For GPIB systems, the Selected Device Clear command is used.
- For a serial device, if VI_ATTR_IO_PROT is VI_ASRL488, the device is sent the string "*CLS\n". This operation is not valid for a serial device if VI_ATTR_IO_PROT is VI_NORMAL.

Note: Invoking viClear() will also discard the read and write buffers used by the formatted I/O services for that session.

See also

Basic Input/Output VI_ATTR_IO_PROT

viClose (vi)

Usage

Closes the specified session, event, or find list.

C format

ViStatus viClose (ViObject vi)

Visual basic format

viClose (ByVal vi As Long) As Long

Parameters

Table 18: viClose() Parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session, event, or find list.

Return values

Table 19: viClose() completion codes

Completion codes	Description
VI_SUCCESS	Session, event, or find list closed successfully.
Table continued	

Completion codes	Description
VI_WARN_NULL_OBJECT	The specified object reference is uninitialized.
	This message is returned if the value VI_NULL is passed to it.
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_CLOSING_FAILED	Unable to deallocate the previously allocated data structures corresponding to this session or object reference.

C example

```
ViSession rm, vi;
if (viOpenDefault(&rm) < VI_SUCCESS) return;
if (viOpen(rm, "GPIB8::1::INSTR", VI_NULL, VI_NULL, &vi)
< VI_SUCCESS) return;
viClose(vi);
viClose(rm);
```

Comments

The viClose() operation closes a session, event, or a find list, and frees all data structures allocated for the specified vi.

See also

Opening and Closing Sessions, Events, and Find Lists viOpen (sesn, rsrcName, accessMode, timeout, vi) viOpenDefaultRM (sesn)

viDisableEvent (vi, eventType, mechanism)

Usage

Disables notification of the specified event using the specified mechanism.

C format

ViStatus viDisableEvent (ViSession vi, ViEventType eventType, ViUInt16 mechanism)

Visual basic format

```
viDisableEvent (ByVal vi As Long, ByVal EventType As Long, ByVal mechanism As Integer) As Long
```

Parameters

Table 20: viDisableEvent() Parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
eventType	IN	Logical event identifier.
mechanism	IN	Specifies event handling mechanisms to be disabled. The queuing mechanism is disabled by specifying VI_QUEUE, and the callback mechanism is disabled by specifying VI_HNDLR or VI_SUSPEND_HNDLR. It is possible to disable both mechanisms simultaneously by specifying VI_ALL_MECH.

Table 21: viDisableEvent() completion codes

Completion codes	Description
VI_SUCCESS	Event disabled successfully.
VI_SUCCESS_EVENT_DIS	Specified event is already disabled for at least one of the specified mechanisms.

Table 22: viDisableEvent() error codes

Error codes	Description
VI_ERROR_INV_SESSION VI_ERROR_INV_OBJECT	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_EVENT	Specified event type is not supported by the resource.
VI_ERROR_INV_MECH	Invalid mechanism specified.

C example

ViSession rm, vi; if (viOpenDefaultRM(&rm) < VI_SUCCESS) return; if (viOpen(rm, "GPIB8::1::INSTR", NULL, NULL, &vi) < VI_SUCCESS) return; viEnableEvent(vi, VI_EVENT_SERVICE_REQ, VI_QUEUE, VI_NULL); // Do some processing here // Cleanup and exit viDisableEvent(vi, VI_EVENT_SERVICE_REQ, VI_QUEUE); viClose(vi); viClose(rm);

Comments

The viDisableEvent() operation disables servicing of an event identified by eventType for the mechanisms specified in mechanism.

This operation prevents new event occurrences from being added to the queue(s); however, event occurrences already existing in the queue(s) are not flushed. Use viDiscardEvents() if you want to discard events remaining in the queue(s).

Table 23: Special Values for eventtype parameter with viDisableEvent()

Value	Description
VI_ALL_ENABLED_EVENTS	Disable all events that were previously enabled. Allows a session to stop receiving all events.

Table 24: Special values for mechanism parameter with viDisableEvent()

Value	Description
VI_QUEUE	Disable this session from receiving the specified event(s) via the waiting queue. Stops the session from receiving queued events.
	Disable this session from receiving the specified event(s) via a callback handler or a callback queue. Specifying either VI_HNDLR or VI_SUSPEND_HNDLR stops applications from receiving callback events.
VI_ALL_MECH	Disable this session from receiving the specified event(s) via any mechanism. Disables both the queuing and callback mechanisms.

See also

```
Handling Events
viEnableEvent (vi, eventType, mechanism, context)
```

viDiscardEvents (vi, eventType, mechanism)

Usage

Discards all pending occurrences of the specified events for the specified mechanism(s) and session.

C format

```
ViStatus viDiscardEvents (ViSession vi, ViEventType eventType, ViUInt16 mechanism)
```

Visual basic format

```
viDiscardEvents (ByVal vi As Long, ByVal EventType As Long, ByVal mechanism As Integer) As Long
```

Parameters

Table 25: viDiscardEvents() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
eventType	IN	Logical event identifier.
mechanism	IN	Specifies event handling mechanisms to be discarded. The VI_QUEUE value is specified for the queuing mechanism and the VI_SUSPEND_HNDLR value is specified for pending events in the callback mechanism. To discard both mechanisms simultaneously, specify VI_ALL_MECH.

Return values

Table 26: viDiscardEvents() completion codes

Completion codes	Description
VI_SUCCESS	Event queue flushed successfully.
VI_SUCCESS_QUEUE_EMPTY	Operation completed successfully, but queue was empty

Table 27: viDiscardEvents() error codes

Error codes	Description
VI_ERROR_INV_SESSION VI_ERROR_INV_OBJECT	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_EVENT	Specified event type is not supported by the resource.
VI_ERROR_INV_MECH	Invalid mechanism specified.

C example

// Cleanup and exit

status = viDiscardEvents(vi, VI_EVENT_SERVICE_REQ, VI_QUEUE);

Comments

The viDiscardEvents() operation discards all pending occurrences of the specified event types and mechanisms from the specified session.

- The discarded event occurrences are not available to a session at a later time.
- · This operation does not apply to event contexts that have already been delivered to the application.

Table 28: Special values for eventtype parameter with viDiscardEvents()

Value	Description
	Discard events of every type enabled for the given session. The information about all the event occurrences which have not yet been handled is discarded. This operation is useful to remove event occurrences that an application no longer needs.

Table 29: Special values for mechanism parameter with viDiscardEvents()

Value	Description
VI_QUEUE	Discard the specified event(s) from the waiting queue.
VI_HNDLR or VI_SUSPEND_HNDLR	Discard the specified event(s) from the callback queue.
VI_ALL_MECH	Discard the specified event(s) from all mechanisms.

See also

Handling Events

viWaitOnEvent (vi, inEventType, timeout, outEventType, outContext)

viEnableEvent (vi, eventType, mechanism, context)

Usage

Enables notification of a specified event.

C format

```
ViStatus viEnableEvent (ViSession vi, ViEventType eventType, ViUInt16 mechanism, viEventFilter context)
```

Visual basic format

```
viEnableEvent (ByVal vi As Long, ByVal EventType As Long, ByVal mechanism As Integer, ByVal context As Long) As Long
```

Parameters

Table 30: viEnableEvent() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
eventType	IN	Logical event identifier.
mechanism	IN	Specifies event handling mechanisms to be enabled. The queuing mechanism is enabled by specifying VI_QUEUE, and the callback mechanism is enabled by specifying VI_HNDLR or VI_SUSPEND_HNDLR. It is possible to enable both mechanisms simultaneously by specifying "bitwise OR" of VI_QUEUE and one of the two mode values for the callbackmechanism.
context	IN	VI_NULL

Return values

Table 31: viEnableEvent() completion codes

Completion codes	Description
VI_SUCCESS	Event enabled successfully.
VI_SUCCESS_EVENT_EN	Specified event is already enabled for at least one of the specified mechanisms.

Table 32: viEnableEvent() error codes

Error codes	Description	
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).	
VI_ERROR_INV_OBJECT		
VI_ERROR_INV_EVENT	Specified event type is not supported by the resource.	
VI_ERROR_INV_MECH	Invalid mechanism specified.	
	Returned if called with the mechanism parameter equal to the "bit-wise OR" of VI_SUSPEND_HNDLR and VI_HNDLR.	
VI_ERROR_INV_CONTEXT	Specified event context is invalid.	
Table continued		

Error codes	Description
	If no handler is installed for the specified event type, the request to enable the callback mechanism for the event type returns this error code. The session cannot be enabled for the VI_HNDLR mode of the callback mechanism.

C example

ViSession rm, vi; if (viOpenDefaultRM(&rm) < VI_SUCCESS) return; if (viOpen(rm, "GPIB8::1::INSTR", NULL, NULL, &vi) < VI_SUCCESS) return; **viEnableEvent(vi, VI_EVENT_SERVICE_REQ, VI_QUEUE, VI_NULL);** // Do some processing here // Cleanup and exit viDisableEvent(vi, VI_EVENT_SERVICE_REQ, VI_QUEUE); viClose(vi); viClose(rm);

Comments

The viEnableEvent() operation enables notification of an event identified by eventType for mechanisms specified in mechanism.

Table 33: Special values for eventtype Parameter with viEnableEvent()

Value	Description
	Switch all events previously enabled on this session to the callback mechanism specified in the mechanism parameter.
	Makes it easier to switch between the two callback mechanisms for multiple events.

Table 34: Special values for mechanism Parameter with viEnableEvent()

Value	Description
VI_QUEUE	Enable this session to receive the specified event via thewaiting queue. Events must be retrieved manually via the viWaitOnEvent() operation.
	Enables the specified session to queue events.
VI_HNDLR	Enable this session to receive the specified event via a callback handler, which must have already been installed via viInstallHandler().
	Enables the session to invoke a callback function to execute the handler. Applications must install at least one handler to be enabled for this mode.
VI_SUSPEND_HNDLR	Enable this session to receive the specified event via a callback queue. Events will not be delivered to the session until viEnableEvent() is invoked again with the VI_HNDLR mechanism.
	Enables the session to receive callbacks, but invocation of the handler is deferred to a later time. Successive calls to this operation replace the old callback mechanism with the new callback mechanism.

• Event queuing and callback mechanisms operate independently. Enabling one mode does not enable or disable the other mode.

- If the mode is switched from VI_SUSPEND_HNDLR to VI_HNDLR for an event type, VISA will call installed handlers once for each event occurrence pending in the session (and dequeued from the suspend handler queue) before switching modes.
- A session enabled to receive events can start receiving them before the viEnableEvent() operation returns. In this case, the handlers set for an event type are executed before completion of the enable operation.
- If the mode is switched from VI_HNDLR to VI_SUSPEND_HNDLR for an event type, VISA will defer handler invocation for occurrences of the event type.
- If a session has events pending in its queue(s) and viClose() is invoked on that session, VISA will free all pending event occurrences and associated contexts not yet delivered to the application for that session.

See also

Handling Events viDisableEvent (vi, EventType, mechanism)

viEventHandler (vi, eventType, context, userHandle)

Usage

Prototype for handler(s) to be called back when a particular event occurs.

C format

```
ViStatus viEventHandler(ViSession vi, ViEventType eventType, ViEvent context, ViAddr userHandle)
```

Visual basic format

Not applicable

Parameters

Table 35: viEventHandler() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
eventType	IN	Logical event identifier.
context	IN	A handle specifying the unique occurrence of an event.
userHandle	IN	A handle specifying the unique occurrence of an event.

Return values

Table 36: viEventHandler() completion codes

Completion codes	Description
VI_SUCCESS	Event handled successfully.
VI_SUCCESS_NCHAIN	Event handled successfully. Do not invoke any other handlers on this session for this event.

C example

```
ViStatus VI FUNCH ServiceReqEventHandler(ViSession vi, ViEventType
eventType, ViEvent event, ViAddr userHandle)
ł
printf("srq occurred\n");
return VI SUCCESS;
int main(int argc, char* argv[])
ViSession rm, vi;
ViStatus status;
char string[256];
ViUInt32 retCnt;
status = viOpenDefaultRM(&rm);
if (status < VI SUCCESS) goto error;
status = viOpen(rm, "GPIB8::1::INSTR", NULL, NULL, &vi);
if (status < VI SUCCESS) goto error;
// Setup and enable event handler
status = viInstallHandler(vi, VI EVENT SERVICE REQ,
ServiceReqEventHandler, NULL);
if (status < VI SUCCESS) goto error;
status = viEnableEvent(vi, VI EVENT SERVICE REQ,
VI HNDLR. VI NULL):
if (status < VI SUCCESS) goto error;
// Do processing here
// Cleanup and exit
status = viDisableEvent(vi, VI_EVENT_SERVICE_REQ, VI_HNDLR);
if (status < VI SUCCESS) goto error;
status = viUninstallHandler(vi, VI EVENT SERVICE REQ,
ServiceReqEventHandler, NULL);
if (status < VI SUCCESS) goto error;
viClose(vi);
viClose(rm);
```

Comments

viEventHandler() is the prototype for a user event handler that is installed with the viInstallHandler() operation. The user handler is called whenever a session receives an event and is enabled for handling events in the VI_HNDLR mode. The handler services the event and returns VI_SUCCESS on completion. Because each event type defines its own context in terms of attributes, refer to the appropriate event definition to determine which attributes can be retrieved using the context parameter.

- The VISA system automatically invokes the viClose() operation on the event context when a user handler returns. Because the event
 context must still be valid after the user handler returns (so that VISA can free it up), do not invoke the viClose() operation on an event
 context passed to a user handler. However, if the user handler will not return to VISA, call viClose() on the event context to manually
 delete the event object. This situation may occur when a handler throws a C++ exception in response to a VISA exception event.
- Normally, you should always return VI_SUCCESS from all callback handlers, since future versions or implementations of VISA may
 take actions based on other return values. However, if a specific handler does not want other handlers to be invoked for the given
 event for the given session, you should return VI_SUCCESS_NCHAIN. No return value from a handler on one session will affect
 callbacks on other sessions.

See also

Handling Events

vilnstallHandler (vi, eventType, handler, userHandle) viUninstallHandler (vi, eventType, handler, userHandle)

viFindNext (findList, instrDesc)

Usage

Returns the next resource from the find list.

C format

ViStatus viFindNext(ViFindList findList, ViPRsrc instrDesc[])

Visual basic format

viFindNext (ByVal findList As Long, ByVal instrDesc As String) As Long

Parameters

Table 37: viFindNext() parameters

Name	Direction	Description
findList	IN	Describes a find list. This parameter must be created by viFindRsrc().
instrDesc		Returns a string identifying the location of a device. Strings can then be passed to viOpen() to establish a session to the given device.

Return values

Table 38: viFindNext() completion codes

Completion codes	Description
VI_SUCCESS	Resource(s) found.

Table 39: viFindNext() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_NSUP_OPER	The given findList does not support this operation.
VI_ERROR_RSRC_NFOUND	There are no more matches.

C example

ViSession rm, vi; ViStatus status; ViChar desc[256], id[256], buffer[256]; ViUInt32 retCnt, itemCnt; ViFindList list;

```
ViUInt32 i;
// Open a default Session
status = viOpenDefaultRM(&rm);
if (status < VI SUCCESS) goto error;
// Find all GPIB devices
status = viFindRsrc(rm, "GPIB?*INSTR", &list, &itemCnt, desc);
if (status < VI SUCCESS) goto error;
for (i = 0; i < itemCnt; i++) {
// Open resource found in rsrc list
status = viOpen(rm, desc, VI NULL, VI NULL, &vi);
if (status < VI SUCCESS) goto error;
// Send an ID query.
status = viWrite(vi, (ViBuf) "*idn", 5, &retCnt);
if (status < VI SUCCESS) goto error;
// Clear the buffer and read the response
status = viRead(vi, (ViBuf) id, sizeof(id), &retCnt);
id[retCnt] = '\0';
if (status < VI SUCCESS) goto error;
// Print the response
printf("id: %s: %s\n", desc, id);
// We're done with this device so close it
viClose(vi);
// Get the next item
viFindNext(list, desc);
}
// Clean up
viClose(rm);
```

Comments

The viFindNext() operation returns the next device found in the list created by viFindRsrc(). The list is referenced by the handle returned by viFindRsrc().



Note: The size of the instrDesc parameter should be at least 256 bytes.

See also

Finding Resources viFindRsrc (sesn, expr, findList, retcnt, instrDesc)

viFindRsrc (sesn, expr, findList, retCount, instrDesc)

Usage

Find a list of resources associated with a specified interface.

C format

```
ViStatus viFindRsrc(ViSession sesn, ViConstString expr, ViPFindList findList,
ViPUInt32 retCount, ViPRsrc instrDesc[])
```

Visual basic format

viFindRsrc (ByVal sesn As Long, ByVal expr As String, ByVal findList As Long, ByVal retCount As Long, ByVal instrDesc As String) As Long

Parameters

Table 40: viFindRsrc() parameters

Name	Direction	Description
sesn	IN	Resource Manager session (should always be the Default Resource Manager for VISA returned from viOpenDefaultRM())
expr	IN	This is a regular expression followed by an optional logical expression. The grammar for this expression is given below.
findList	OUT	Returns a handle identifying this search session. This handle will be used as an input in viFindNext().
retCount	OUT	Number of matches.
instrDesc	OUT	Returns a string identifying the location of a device. Strings can then be passed to viOpen() to establish a session to the given device.

Return values

Table 41: viFindRsrc() completion codes

Completion codes	Description
VI_SUCCESS	Resource(s) found.

Table 42: viFindRsrc() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_NSUP_OPER	The given sesn does not support this operation.
VI_ERROR_INV_EXPR	Invalid expression specified for search.
VI_ERROR_RSRC_NFOUND	Specified expression does not match any devices.

C example for INSTR resource

ViSession rm, vi; ViStatus status; ViChar desc[256], id[256], buffer[256]; ViUInt32 retCnt, itemCnt; ViFindList list; ViUInt32 i; // Open a default Session status = viOpenDefaultRM(&rm); if (status < VI_SUCCESS) goto error; // Find all GPIB devices

status = viFindRsrc(rm, "GPIB?*INSTR", &list, &itemCnt, desc); if (status < VI SUCCESS) goto error; for (i = 0; i < itemCnt; i++) { // Open resource found in rsrc list status = viOpen(rm, desc, VI NULL, VI NULL, &vi); if (status < VI SUCCESS) goto error; // Send an ID query. status = viWrite(vi, (ViBuf) "*idn?", 5, &retCnt); if (status < VI SUCCESS) goto error; // Clear the buffer and read the response status = viRead(vi, (ViBuf) id, sizeof(id), &retCnt); $id[retCnt] = '\0';$ if (status < VI SUCCESS) goto error; // Print the response printf("id: %s: %s\n", desc, id); // We're done with this device so close it viClose(vi);// Get the next item viFindNext(list, desc); } // Clean up viClose(rm);

C example for socket resource

```
ViSession rm, vi;
ViStatus status:
ViChar desc[256], id[256], buffer[256];
ViUInt32 retCnt, itemCnt;
ViFindList list;
ViUInt32 i:
// Open a default Session
status = viOpenDefaultRM(&rm);
if (status < VI SUCCESS) goto error;
// Find all TCPIP SOCKET devices
status = viFindRsrc(rm, "TCPIP?*SOCKET", &list, &itemCnt, desc);
if (status < VI SUCCESS) goto error;
for (i = 0; i < itemCnt; i++) {
// Open resource found in rsrc list
status = viOpen(rm, desc, VI NULL, VI NULL, &vi);
if (status < VI SUCCESS) goto error;
// Send an ID query.
status = viWrite(vi, (ViBuf) "*idn?", 5, &retCnt);
if (status < VI SUCCESS) goto error;
// Clear the buffer and read the response
status = viRead(vi, (ViBuf) id, sizeof(id), &retCnt);
id[retCnt] = '\0';
if (status < VI SUCCESS) goto error;
// Print the response
printf("id: %s: %s\n", desc, id);
// We're done with this device so close it
viClose(vi);
// Get the next item
viFindNext(list, desc);
```

}
// Clean up
viClose(rm);

Comments

The viFindRsrc() operation matches the value specified in expr with the resources available for a particular interface. On successful completion, this function returns the first resource found in the list (instrDesc).



Note: The size of the instrDesc parameter should be at least 256 bytes.

- This function also returns a count (retcnt) to indicate if more resources were found, and returns a handle to the list of resources (findList). This handle must be used as an input to viFindNext() and should be passed to viClose() when it is no longer needed.
- The retcnt and findList parameters can optionally be omitted if. only the first match is important and the number of matches is not needed.

Table 43: Special value for retCount parameter with viFindRsrc()

Value	Description
VI_NULL	If you pass this value, VISA does not return the number of matches.

Table 44: Special value for findList parameter with viFindRsrc()

Value	Description
_	If you pass this value and the operation completes successfully, VISA does not return the findList handle and invokes viClose() on the handle instead.

• The search criteria specified in the expr parameter has two parts: a regular expression over a resource string, and an optional logical expression over attribute values. A regular expression is a string consisting of ordinary characters as well as special characters.

Special characters and operators	Meaning
?	Matches any one character.
/	Makes the character that follows it an ordinary character instead of special character. For example, when a question mark follows a backslash (\?), it matches the ? character instead of any one character.
[list]	Matches any one character from the enclosed list. You can use a hyphen to match a range of characters.
[^list]	Matches any character not in the enclosed list. You can use a hyphen to match a range of characters.
*	Matches 0 or more occurrences of the preceding character or expression.
+	Matches 1 or more occurrences of the preceding character or expression.
explexp	Matches either the preceding or following expression. The or operator matches the entire expression that precedes or follows it and not just the character that precedes or follows it. For example, ASRL GPIB means (ASRL) (GPIB), not ASR(L G)PIB.
(exp)	Grouping characters or expressions.

Table 45: Regular expression special characters and operators

• You use a regular expression to specify patterns to match in a given string. The regular expression is matched against the resource strings of resources known to the VISA Resource Manager.

 The viFindRsrc() operation uses a case-insensitive compare feature when matching resource names against the regular expression specified in expr. For example, calling viFindRsrc() with "GPIB?*INSTR" would return the same resources as invoking it with "gpib? *instr".

Regular expression	Sample matches
GPIB?*INSTR	Matches GPIB0::2::INSTR and GPIB1::1::I::INSTR.
GPIB[09]*::?*INSTR	Matches GPIB0::2::INSTR and GPIB1::1::1::INSTR
GPIB[09]::?*INSTR	Matches GPIB0::2::INSTR and GPIB1::1::1::INSTR but not GPIB12::8::INSTR.
GPIB[^0]::?*INSTR	Matches GPIB1::1::1::INSTR but not GPIB0::2::INSTR or GPIB12::8::INSTR.
ASRL[09]*::?*INSTR	Matches ASRL1::INSTR but not GPIB0::5::INSTR.
ASRL1+::INSTR	Matches ASRL1::INSTR and ASRL11::INSTR but not ASRL2::INSTR.
?*INSTR	Matches all INSTR (device) resources.
?*	Matches all resources.
TCPIP?*SOCKET	Matches all TCPIP SOCKET resources.

- If the resource string matches the regular expression, the attribute values of the resource are then matched against the expression over attribute values. If the match is successful, the resource has met the search criteria and gets added to the list of resources found.
- The optional attribute expression allows construction of flexible and powerful expressions with the use of logical ANDs, ORs and NOTs. Equal (==) and unequal (!=) comparators can be used compare attributes of any type, and in addition, other inequality comparators (>, <, >=, <=) can be used to compare attributes of numeric type. If the attribute type is ViString, a regular expression can be used in matching the attribute. Only global attributes can be used in the attribute expression.

Table 47: Examples that include attribute expression matches

Expr	Meaning
GPIB[09]*::?*::NSTR{VI_ATTR_GPIB_SECONDARY_ADDR > 0}	Find all GPIB devices that have secondary addresses greater than 0.
ASRL?*INSTR{VI_ATTR_ASRL_BAUD == 9600}	Find all serial ports configured at 9600 baud.
?*ASRL?*INSTR{VI_ATTR_MANF_ID == 0xFF6 &&! (VI_ATTR_ASRL_LA == 0 VI_ATTR_SLOT <= 0)}	Find all ASRL instrument resources whose manufacturer ID is FF6 and who are not logical address 0, slot 0, or external controllers.

See also

Finding Resources viFindNext (findList, instrDesc)

viFlush (vi, mask)

Usage

Manually flushes the specified buffer(s).

C format

ViStatus viFlush (ViSession vi, ViUint16 mask)

Visual basic format

viFlush (ByVal vi As Long, ByVal mask As Integer) As Long

Parameters

Table 48: viFlush() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
mask	IN	Specifies the action to be taken with flushing the buffer.

Return values

Table 49: viFlush() completion codes

Completion codes	Description
VI_SUCCESS	Buffers flushed successfully.

Table 50: viFlush() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_IO	Could not perform read/write operation because of I/O error.
VI_ERROR_TMO	The read/write operation was aborted because timeout expired while operation was in progress.
VI_ERROR_INV_MASK	The specified mask does not specify a valid flush operation on read/write resource.

C example

// Request the curve
status = viPrintf(vi, "CURVE?\n");
if (status < VI_SUCCESS) goto error;
// Always flush if a viScanf follows a viPrintf or
// viBufWrite.
status = viFlush(vi, VI_WRITE_BUF | VI_READ_BUF_DISCARD);
if (status < VI_SUCCESS) goto error;
// Get first char and validate
status = viScanf(vi, "%c", &c);</pre>

Comments

The value of mask can be one of the following flags:

Table 51: viFlush values for mask parameter

Flag	Meaning
VI_READ_BUF	Discard the read buffer contents. If data was present in the read buffer and no ENDindicator was present, read from the device until encountering an END indicator (which causes the loss of data). This action resynchronizes the next viScanf() call to read a <terminated message="" response="">. (Refer to the IEEE 488.2 standard.)</terminated>
VI_READ_BUF_DISCARD	Discard the read buffer contents (does not perform any I/O to the device).
VI_WRITE_BUF	Flush the write buffer by writing all buffered data to the device.
VI_WRITE_BUF_DISCARD	Discard the write buffer contents (does not perform any I/O to the device).
VI_ASRL_IN_BUF	Discard the receive buffer contents (same asVI_ASRL_IN_BUF_DISCARD).
VI_ASRL_IN_BUF_DISCARD	Discard the receive buffer contents (does not perform any I/O to the device)
VI_ASRL_OUT_BUF	Flush the transmit buffer by writing all buffered data to the device.
VI_ASRL_OUT_BUF_DISCARD	Discard the transmit buffer contents (does not perform any I/O to the device).

• It is possible to combine any of these read flags and write flags for different buffers by ORing the flags. However, combining two flags for the same buffer in the same call to viFlush() is illegal.

 Notice that when using formatted I/O operations with a serial device, a flush of the formatted I/O buffers also causes the corresponding serial communication buffers to be flushed. For example, calling viFlush() with VI_WRITE_BUF also flushes the VI_ASRL_OUT_BUF.

See also

Reading and Writing Formatted Data viSetBuf (vi, mask, size)

viGetAttribute (vi, attribute, attrState)

Usage

Retrieves the state of an attribute for the specified session, event, or find list.

C format

```
ViStatus viGetAttribute(ViObject vi, ViAttr attribute, ViAttrState attrState)
```

Visual basic format

```
viGetAttribute (ByVal vi As Long, ByVal attribute As Long, ByVal attrState As Long) As Long
```

Parameters

Table 52: viGetAttribute() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session, event, or find list.
attribute	IN	Session, event, or find list attribute for which the state query is made.

Table continued...

Name	Direction	Description
attrState	OUT	The state of the queried attribute for a specified resource. The interpretation of the returned value is defined by the individual resource.

Return values

Table 53: viGetAttribute() completion codes

Completion codes	Description
VI_SUCCESS	Session, event, or find list attribute retrieved successfully.

Table 54: viGetAttribute() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_NSUP_ATTR	The specified attribute is not defined by the referenced session, event, or find list.

C example

```
// Get VISA's vendors name, VISA Specification
// Version, and implementation version.
status = viGetAttribute(rm, VI_ATTR_RSRC_MANF_NAME, buffer);
if (status < VI_SUCCESS) goto error;
status = viGetAttribute(rm, VI_ATTR_RSRC_SPEC_VERSION,
&version);
if (status < VI_SUCCESS) goto error;
status = viGetAttribute(rm, VI_ATTR_RSRC_IMPL_VERSION,
&impl);
if (status < VI_SUCCESS) goto error;</pre>
```

Comments

tThe viGetAttribute() operation is used to retrieve the state of an attribute for the specified session, event, or find list.

The output parameter attrState is of the type of the attribute actually being retrieved. For example, when retrieving an attribute defined as a ViBoolean, your application should pass a reference to a variable of type ViBoolean. Similarly, if the attribute is defined as being ViUInt32, your application should pass a reference to a variable of type ViUInt32.

See also

Setting and Retrieving Attributes viSetAttribute (vi, attribute, attrState)

viGpibCommand (vi, buf, count, retCount)

Usage

Write GPIB command bytes on the bus.

C format

```
ViStatus status; ViSession vi,rm; ViUInt32 retCnt; status = viGpibCommand(vi,
(ViConstBuf)"*IDN?", 5, &retCnt);
```

Parameters

Table 55: viGpibCommand() parameters

Name	Direction	Туре	Description
vi	IN	ViSession	Unique logical identifer to a session.
buf	IN	ViConstBuf	Buffer containing valid GPIB commands.
count	IN	ViUInt32	Number of bytes to be written.
retCount	OUT	ViUInt32	Number of bytes actually transferred.

Return values

Type Vistatus: This is the operational return status. It returns either a completion code or an error code as follows.

Table 56: viGpibCommand() completion codes

Completion code	Description
VI_SUCCESS	Operation completed successfully.

Table 57: viGpibCommand() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_NSUP_OPER	The given vi does not support this operation.
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked by this kind of access.
VI_ERROR_TMO	Timeout expired before operation completed.
VI_ERROR_INV_SETUP	Unable to start write operation because setup is invalid (due to attributes being set to an inconsistent state).
VI_ERROR_NCIC	The interference associated with the given vi is not currently the controller in charge.
VI_ERROR_NLISTENERS	No Listereners condition is detected (both NRFD and NADC are deasserted).
VI_ERROR_IO	An unknown I/O error occurred during transfer.

vilnstallHandler (vi, eventType, handler, userHandle)

Usage

Installs callback handler(s) for the specified event.

C format

```
ViStatus viInstallHandler (ViSession vi, ViEventType eventType, ViHndlr handler, ViAddr userHandle)
```

Visual basic format

Not Applicable

Parameters

Table 58: vilnstallHandler() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
eventType	IN	Logical event identifier.
handler	IN	Interpreted as a valid reference to a handler to be installed by a client application.
userHandle		A value specified by an application that can be used for identifying handlers uniquely for an event type.

Return values

Table 59: vilnstallHandler() completion codes

Completion codes	Description
VI_SUCCESS	Event handler installed successfully.

Table 60: vilnstallHandler() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_INV_EVENT	Specified event type is not supported by the resource.
VI_ERROR_INV_HNDLR_REF	The given handler reference is invalid.
VI_ERROR_HNDLR_NINSTALLED	The handler was not installed. This may be returned if an application attempts to install multiple handlers for the same event on the same session.

C example

```
ViStatus _VI_FUNCH ServiceReqEventHandler(ViSession vi, ViEventType eventType,
ViEvent event, ViAddr userHandle)
{
printf("srq occurred\n");
return VI_SUCCESS;
}
int main(int argc, char* argv[])
{
ViSession rm, vi;
ViStatus status;
```

```
char string[256];
ViUInt32 retCnt:
status = viOpenDefaultRM(&rm);
if (status < VI SUCCESS) goto error;
status = viOpen(rm, "GPIB8::1::INSTR", NULL, NULL,
&vi):
if (status < VI SUCCESS) goto error;
// Setup and enable event handler
status = viInstallHandler(vi, VI EVENT SERVICE REQ,
ServiceReqEventHandler, NULL);
if (status < VI SUCCESS) goto error;
status = viEnableEvent(vi, VI EVENT SERVICE REQ,
VI HNDLR, VI NULL);
if (status < VI SUCCESS) goto error;
// Do processing here
// Cleanup and exit
status = viDisableEvent(vi, VI EVENT SERVICE REQ,
VI HNDLR);
if (status < VI SUCCESS) goto error;
status = viUninstallHandler(vi, VI EVENT SERVICE REQ,
ServiceReqEventHandler, NULL);
if (status < VI SUCCESS) goto error;
viClose(vi);
viClose(rm);
return 0;
error:
viStatusDesc(rm, status, string);
fprintf(stderr, "Error: %s\n", (ViBuf) string);
return 0;
}
```

Comments

The vilnstallHandler() operation allows applications to install handlers on sessions. The handler specified in handler is installed along with any previously installed handlers for the specified event.

- You can specify a value in userHandle that is passed to the handler on its invocation. VISA identifies handlers uniquely using the handler reference and this value.
- VISA allows you to install multiple handlers for an event type on the same session. You can install multiple handlers through multiple invocations of the vilnstallHandler() operation, where each invocation adds to the previous list of handlers. If more than one handler is installed for an event type, each handlers is invoked on every occurrence of the specified event(s). Handlers are invoked in Last In First Out (LIFO) order

See also

Handling Events

viUninstallHandler (vi, eventType, handler, userHandle)

viLock (vi, lockType, timeout, requestedKey, accessKey)

Usage

Obtains a lock on the specified resource.

C format

```
ViStatus viLock(ViSession vi, ViAccessMode lockType, ViUInt32 timeout, ViConstKeyId requestedKey, ViPKeyId accessKey[])
```

Visual basic format

viLock (ByVal vi As Long, ByVal lockType As Long, ByVal timeout As Long, ByValrequestedKey As String, ByVal accessKey As String) As Long

Parameters

Table 61: viLock() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
lockType	IN	Specifies the type of lock requested, which can be either VI_EXCLUSIVE_LOCK or VI_SHARED_LOCK.
timeout	IN	Absolute time period (in milliseconds) that a resource waits to get unlocked by the locking session before returning this operation with an error.
requestedKey	IN	This parameter is not used and should be set to VI_NULL when lockType is VI_EXCLUSIVE_LOCK (exclusive locks). When trying to lock the resource as VI_SHARED_LOCK (shared), a session can either set it to VI_NULL, so that VISA generates an accessKey for the session, or the session can suggest an accessKey to use for the shared lock. Refer to the comments section below for more details.
accessKey	OUT	This parameter should be set to VI_NULL when lockType is VI_EXCLUSIVE_LOCK (exclusive locks). When trying to lock the resource as VI_SHARED_LOCK (shared), the resource returns a unique access key for the lock if the operation succeeds. This accessKey can then be passed to other sessions to share the lock.

Return values

Table 62: viLock() completion codes

Completion codes	Description
VI_SUCCESS	Specified access mode is successfully acquired.
VI_SUCCESS_NESTED_EXCLUSIVE	Specified access mode is successfully acquired, and this session has nested exclusive locks.
VI_SUCCESS_NESTED_SHARED	Specified access mode is successfully acquired, and this session has nested shared locks.

Table 63: viLock() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
Table continued	

Table continued...

Error codes	Description
VI_ERROR_RSRC_LOCKED	Specified type of lock cannot be obtained because the resource is already locked with a lock type incompatible with the lock requested. For example, this error is returned if a viLock() operation requesting a shared lock is invoked from a session that has an exclusive lock.
VI_ERROR_INV_LOCK_TYPE	The specified type of lock is not supported by this resource.
VI_ERROR_INV_ACCESS_KEY	The requestedKey value passed in is not a valid access key to the specified resource.
VI_ERROR_TMO	Specified type of lock could not be obtained within the specified timeout period.

C example

```
ViSession rm, vi;
char string[256];
ViUInt32 retCnt;
int i = 0;
if (viOpenDefaultRM(&rm) < VI SUCCESS) return;
if (viOpen(rm, "GPIB8::1::INSTR", NULL, NULL, &vi) < VI_SUCCESS)
return;
for (i = 1; i < 100; i++)
viLock(vi, VI EXCLUSIVE LOCK, VI TMO INFINITE, NULL,
NULL);
if (viWrite(vi, (ViBuf) "ch1:scale?", 10, &retCnt)
< VI SUCCESS) return;
if (viRead(vi, (ViBuf) string, 256, &retCnt)
< VI SUCCESS) return;
printf("%d: scale %s", i, string);
viUnlock(vi);
}
```

Comments

This operation is used to obtain a lock on the specified resource. The caller can specify the type of lock requested—exclusive or shared lock—and the length of time the operation will suspend while waiting to acquire the lock before timing out. This operation can also be used for sharing and nesting locks.



Note: If requesting a VI_SHARED_LOCK, the size of the accessKey parameter should be at least 256 bytes.

- The requestedKey and the accessKey parameters apply only to shared locks. When using the lock type VI_EXCLUSIVE_LOCK, requestedKey and accessKey should be set to VI_NULL.
- VISA allows you to specify a key to be used for lock sharing through the use of the requestedKey parameter. Or, you can pass VI_NULL for requestedKey when obtaining a shared lock, in which case VISA will generate a unique access key and return it through accessKey. If you do specify a requestedKey, VISA will try to use this value for the accessKey. As long as the resource is not locked, VISA will use the requestedKey as the access key and grant the lock. When the operation succeeds, the requestedKey will be copied into the user buffer referred to by the accessKey.
- The session that gained a shared lock can pass the accessKey to other sessions for the purpose of sharing the lock. The session
 wanting to join the group of sessions sharing the lock can use the key as an input value to the requestedKey parameter. VISA will add
 the session to the list of sessions sharing the lock, as long as the requestedKey value matches the accessKey value for the particular
 resource. The session obtaining a shared lock in this manner will then have the same access privileges as the original session that
 obtained the lock.

You can obtain nested locks through this operation. To acquire nested locks, invoke the viLock() operation with the same lock type
as the previous invocation of this operation. For each session, viLock() and viUnlock() share a lock count, which is initialized to 0.
Each invocation of viLock() for the same session (and for the same lockType) increases the lock count. In the case of a shared lock, it
returns with the same accessKey every time.

When a session locks the resource a multiple number of times, you must invoke the viUnlock() operation an equal number of times in order to unlock the resource. That is, the lock count increments for each invocation of viLock(), and decrements for each invocation of viUnlock(). A resource is actually unlocked only when the lock count is 0.

See also

Locking and Unlocking Resources viUnlock (vi)

viOpen (sesn, rsrcName, accessMode, timeout, vi)

Usage

Opens a session to the specified resource.

C format

```
ViStatus viOpen(ViSession sesn, ViConstRsrc name, ViAccessMode mode, ViUInt32 timeout, ViPSession vi)
```

Visual basic format

viOpen (ByVal sesn As Long, ByVal rsrcName As String, ByVal accessMode As Long, ByVal timeout As Long, vi As Long) As Long

Parameters

Table 64: viOpen() parameters

Name	Direction	Description
sesn	IN	Resource manager session (should always be the default resource manager for VISA returned from viOpenDefaultRM()).
rsrcName	IN	Unique symbolic name of a resource.
accessMode	IN	Specifies the mode(s) by which the resource is to be accessed: VI_EXCLUSIVE_LOCK and/or VI_LOAD_CONFIG. If the latter value is not used, the session uses the default values provided by VISA. Multiple access modes can be used simultaneously by specifying a "bit-wise OR" of the above values.
timeout	IN	If the accessMode parameter requests a lock, then this parameter specifies the absolute time period (in milliseconds) that the resource waits to get unlocked before this operation returns an error; otherwise, this parameter is ignored.
vi	OUT	Unique logical identifier reference to a session.

Return values

Table 65: viOpen() completion codes

Completion codes	Description
VI_SUCCESS	Session opened successfully.
VI_SUCCESS_DEV_NPRESENT	Session opened successfully, but the device at the specified address is not responding.
	The specified configuration either does not exist or could not be loaded; using VISA-specified defaults instead.

Table 66: viOpen() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_INV_RSRC_NAME	Invalid resource reference specified. Parsing error.
VI_ERROR_INV_ACC_MODE	Invalid access mode.
VI_ERROR_RSRC_NFOUND	Insufficient location information or resource not present in the system.
VI_ERROR_ALLOC	Insufficient system resources to open a session.
VI_ERROR_RSRC_BUSY	The resource is valid, but VISA cannot currently access it.
VI_ERROR_RSRC_LOCKED	Specified type of lock cannot be obtained because the resource is already locked with a lock type incompatible with the lock requested.
VI_ERROR_TMO	A session to the resource could not be obtained within the specified timeout period.
VI_ERROR_LIBRARY_NFOUND	A code library required by VISA could not be located or loaded.

C example

// Open the GPIB device at primary address 1, GPIB board 8
status = viOpen(rm, "GPIB8::1::INSTR", VI_NULL, VI_NULL,
&vi);
if (status < VI_SUCCESS) goto error;</pre>

Comments

The viOpen() operation opens a session to the specified resource. It returns a session identifier that can be used to call any other operations of that resource.

- The GPIB keyword can be used to establish communication with a GPIB device.
- The ASRL keyword is used to establish communication with an asynchronous serial device (such as RS-232).
- An address string must uniquely identify the resource. The following table shows the grammar for the address string and gives examples.
 - Optional string segments are shown in square brackets ([]).
 - The default value for the optional string segment board is 0.
 - The default value for the optional string segment secondary address is none.
 - Address strings are not case sensitive.

Table 67: Resource address string grammar and examples with viOpen()

Grammar	Example	Description
GPIB[board]:: primary address[:: secondary address][::INSTR]	GPIB::1::0::INSTR	A GPIB device at primary address 1 and secondary address 0 in GPIB interface 0.
ASRL[board][::INSTR]	ASRL1::INSTR	A serial device attached to interface ASRL1.

Table 68: Special values for accessmode parameter with viOpen()

Value	Description
	Used to acquire an exclusive lock immediately upon opening a session; if a lock cannot be acquired, the session is closed and an error is returned.
VI_LOAD_CONFIG	Used to configure attributes to values specified by an external configuration utility.

See also

Opening and Closing Sessions viOpenDefaultRM (sesn) viClose (vi)

viOpenDefaultRM (sesn)

Usage

Returns a session to the Default Resource Manager.

C format

ViStatus viOpenDefaultRM(ViSession sesn)

Visual basic format

viOpenDefaultRM (ByVal sesn As Long) As Long

Parameters

Table 69: viOpenDefaultRM() parameters

Name	Direction	Description
sesn	OUT	Unique logical identifier to a Default Resource Manager session.

Return values

Table 70: viOpenDefaultRM() completion codes

Completion codes	Description
VI_SUCCESS	Session to the Default Resource Manager resource created successfully.

Table 71: viOpenDefaultRM() error codes

Error codes	Description
VI_ERROR_SYSTEM_ERROR	The VISA system failed to initialize.
VI_ERROR_ALLOC	Insufficient system resources to create a session to the Default Resource Manager resource.
VI_ERROR_INV_SETUP	Some implementation-specific configuration file is corrupt or does not exist.
VI_ERROR_LIBRARY_NFOUND	A code library required by VISA could not be located or loaded.

C example

// Open a default session
status = viOpenDefaultRM(&rm);
if (status < VI_SUCCESS) goto error;</pre>

Comments

The viOpenDefaultRM() function must be called before any VISA operations can be invoked.

- The first call to this function initializes the VISA system, including the Default Resource Manager resource, and also returns a session to that resource.
- · Subsequent calls to this function return new and unique sessions to the same Default Resource Manager resource.
- When a Resource Manager session is closed, all find lists and device sessions opened with that Resource Manager session are also closed.

See also

Opening and Closing Sessions viOpen (sesn, rsrcName, accessMode, timeout, vi) viClose (vi)

viParseRsrc (sesn, rsrcName, intfType, intfNum)

Usage

Parses a resource string to get the interface information.

C format

```
ViStatus viParseRsrc(ViSession sesn, ViConstRsrc rsrcName, ViUint16 intfType, ViUInt intfNum)
```

Visual basic format

viParseRsrc (ByVal sesn As Long, ByVal rsrcName As String, ByVal intfType As Integer, ByVal intfNum As Integer) As Long

Parameters

Table 72: viParseRsrc() parameters

Name	Direction	Description
sesn	IN	Resource Manager session (should always be the Default Resource Manager for VISA returned from viOpenDefaultRM())
rsrcName	IN	Unique symbolic name of a resource.
intfType	OUT	Interface type of the given resource string.
intfNum	OUT	Board number of the interface of the given resource string.

Return values

Table 73: viParseRsrc() completion codes

Completion codes	Description
VI_SUCCESS	Resource string is valid.

Table 74: viParseRsrc() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_NSUP_OPER	The given session does not support this operation. For VISA, this operation is supported only by the Default Resource Manager session.
VI_ERROR_INV_RSRC_NAME	Invalid resource reference specified. Parsing error.
VI_ERROR_RSRC_NFOUND	Insufficient location information or resource not present in the system.
VI_ERROR_ALLO	Insufficient system resources to parse the string.
VI_ERROR_LIBRARY_NFOUND	A code library required by VISA could not be located or loaded.
VI_ERROR_INTF_NUM_NCONFIG	The interface type is valid but the specified interface number is not configured.

C example

```
if (viOpenDefaultRM(&rm) < VI_SUCCESS) return;
if (viParseRsrc(rm,"GPIB8::1::INSTR", ifType, ifNum)) < VI_SUCCESS)
return;
```

Comments

This operation parses a resource string to verify its validity. It should succeed for all strings returned by viFindRsrc() and recognized by viOpen(). This operation is useful if you want to know what interface a given resource descriptor would use without actually opening a session to it.

The values returned in intfType and intfNum correspond to the attributes VI_ATTR_INTF_TYPE and VI_ATTR_INTF_NUM. These values would be the same if a user opened that resource with viOpen() and queried the attributes with viGetAttribute().



Note: The size of the instrDesc parameter should be at least 256 bytes.

- This function returns information determined solely from the resource string and any static configuration information (such as.INI files or the Registry).
- This function is case--insensitive when matching resource names against the name specified in rsrcName. Calling viParseRsrc() with "gpib8::1::instr" will produce the same results as invoking it with "GPIB 8::1::INSTR"..

See also

Finding Resources viFindNext (findList, instrDesc) viFindRsrc (sesn, expr, findList, retcnt, instrDesc)

viParseRsrcEx (sesn, rsrcName, intfType, intfNum, rsrcClass, unaliasedExpandedRsrcName, aliasIfExists)

Usage

Parse a resource string to get extended interface information.

Parameters

Table 75: viParseRsrcEx() parameters

Name	Direction	Туре	Description
sesn	IN	ViSession	Resource Manager session (should always be the Default Resource Manager for VISA returned from <pre>viopenDefaultRM()</pre>).
rsrcName	IN	ViConstRsrc	Unique symbolic name of a resource.
intfType	OUT	ViUInt 16	Interface type of the given resource string.
intfNum	OUT	ViUInt 16	Board number of the interface of the given resource string.
rsrcClass	OUT	ViString	Specifies the resource class (for example, "INSTR") of the given resource string, as defined in Section 5.
Unaliased expanded RsrcName	OUT	ViString	This is the expanded version of the given resource string. The format should be similar to the VISA-defined canonical resource name.
aliaslf Exists	OUT	ViString	Specifies the user-defined alias for the given resource string, if a VISA implementation allows aliases and an alias exists for the given resource string.

Return values

Table 76: viParseRsrcEx() completion codes

Completion codes	Description
VI_SUCCESS	Resource string is valid.
VI_WARN_EXT_FUNC_NIMPL	The operation succeeded, but a lower level driver did not implement the extended functionality.

Error code	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_NSUP_OPER	The given sesn does not support this operation. For VISA, this operation is supported only by the Default Resource Manager session.
VI_EROR_INV_RSRC_NAME	Invalid resource reference specified. Parsing error.
VI_ERROR_RSRC_NFOUND	Insufficient location information or resource not present in the system.
VI_ERROR_ALLOC	Insufficient system resources to parse the string.
VI_ERROR_LIBRARY_NFOUND	A code library required by VISA could not be located or loaded.
VI_ERROR_INTF_NUM_NCONFIG	The interface type is valid but the specified interface number is not configured.

Table 77: viParseRsrcEx() error codes

viPrintf (vi, writeFmt, <arg1, arg2, ...>)

Usage

Formats and writes data to a device using the optional variable-length argument list.

C Format

ViStatus viPrintf (ViSession vi, ViConstString writeFmt, ...)

Visual Basic Format

Not applicable

Parameters

Table 78: viPrintf() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
writeFmt	IN	String describing the format for arguments.
<arg1, arg2,=""></arg1,>	IN	Optional argument(s) the format string is applied to.

Return Values

Table 79: viPrintf() completion codes

Completion codes	Description
VI_SUCCESS	Parameters were successfully formatted.

Table 80: viPrintf() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_IO	Could not perform write operation because of I/O error.
VI_ERROR_TMO	Timeout expired before write operation completed.
VI_ERROR_INV_FMT	A format specifier in the writeFmt string is invalid.
VI_ERROR_NSUP_FMT	A format specifier in the writeFmt string is not supported.
VI_ERROR_ALLOC	The system could not allocate a formatted I/O buffer because of insufficient system resources.

C example

```
// Turn headers off, this makes parsing easier
status = viPrintf(vi, "header off\n");
if (status < VI SUCCESS) goto error;
// Get record length value
status = viQueryf(vi, "hor:reco?\n", "%ld", elements);
if (status < VI SUCCESS) goto error;
// Make sure start, stop values for curve query match the
// full record length
status = viPrintf(vi, "data:start %d;data:stop %d\n", 0,
(*elements)--1);
if (status < VI SUCCESS) goto error;
```

Comments

The viPrintf() operation sends data to a device as specified by the format string (writeFmt). Before sending the data, the operation formats the argument characters as specified in the writeFmt string.

- The viWrite() operation performs the actual low--level I/O to the device. As a result, you should not use the viWrite() and viPrintf() operations in the same session.
- The writeFmt string can include regular character sequences, special formatting characters, and special format specifiers. •
 - The regular characters (including white spaces) are written to the device unchanged. •
 - The special characters consist of ' \' (backslash) followed by a character.
 - The format specifier sequence consists of '%' (percent) followed by an optional modifier (flag), followed by a format code. ٠

Special formatting characters

Special formatting character sequences send special characters. The following table lists the special characters and describes what they send to the device.

Table 81: Special characters used with viPrintf()

Formatting character	Character Sent to Device
\n	Sends the ASCII LF character. The END identifier will also be automatically sent.
Table continued	

|lable continued...

Formatting character	Character Sent to Device
\r	Sends an ASCII CR character.
\t	Sends an ASCII TAB character.
\###	Sends the ASCII character specified by the octal value.
\x##	Sends the ASCII character specified by the hexadecimal value.
\"	Sends the ASCII double-quote (") character.
11	Sends a backslash (\) character.

Format specifiers

The format specifiers convert the next parameter in the sequence according to the modifier and format code, after which the formatted data is written to the specified device. The format specifier takes the following syntax:

%[modifiers]format code

- · Modifiers are optional codes that describe the target data.
- Format code specifies which data type the argument is represented in.
- In the following tables, a 'd' format code refers to all conversion codes of type integer ('d', 'i', 'o', 'u', 'x', 'X'), unless specified as %d only. Similarly, an 'f' format code refers to all conversion codes of type float ('f', 'e', 'E', 'g', 'G'), unless specified as %f only. Every conversion command starts with the % character and ends with a conversion character (format code). Between the % character and the format code, the following modifiers can appear in the sequence.

ANSI C standard modifiers

Table 82: ANSI C standard modifiers used with viPrintf()

Modifier	Supported with Format Code	Description
An integer specifying field width.	d, f, s format codes	This specifies the minimum field width of the converted argument. If an argument is shorter than the field width, it will be padded on theleft (or on the right if the -flag is present).
		Special case: For the @H, @Q, and @B flags, the fieldwidth includes the #H, #Q, and #B strings, respectively.
		An asterisk (*) may be present in lieu of a field width modifier, in which case an extra arg is used. This arg must be an integer representing the field width.
An integer specifying precision.	d, f, s format codes	The precision string consists of a string of decimal digits. A . (decimal point) must prefix specifies the following:
		 The minimum number of digits to appear for the @1, @H, @Q, and @B flags and the i, o, u, x, and X format codes.
		2. The maximum number of digits after the decimal point in case of f format codes.
		3. The maximum numbers of characters for the string (s) specifier.
		4. Maximum significant digits for g formatcode.
		An asterisk (*) may be present in lieu of a precision modifier, in which case an extra arg is used. This arg must be an integer representing the precision of a numeric field.

Table continued...

Modifier	Supported with Format Code	Description
An argument length modifier. h, l, L, z, and Z are legal values. (z and Z are not ANSI C standard modifiers.)	h (d, b, B format codes) I (d, f, b, B format codes) L (f format code) z (b, B format codes) Z (b, B format codes	 The argument length modifiers specify one of the following: The h modifier promotes the argument to a short or unsigned short, depending on the format code type. The I modifier promotes the argument to a long or unsigned long. The L modifier promotes the argument to a long double parameter. The z modifier promotes the argument to an array of floats. The Z modifier promotes the argument to an array of doubles.

Enhanced modifiers to ANSI C standards

Table 83: Enhanced modifiers to ANSI C standards used with viPrintf()

Modifier	Supported with Format Code	Description
A comma (,) followed by an integer n, where n represents the	%d and %f only	The corresponding argument is interpreted as a reference to the first element of an array of size n.
array size.		The first n elements of this list are printed in the format specified by the format code.
		An asterisk (*) may be present after the
		comma (,) modifier, in which case an extra arg is used. This arg must be an integer representing the array size of the given type.
@1	%d and %f only	Converts to an IEEE 488.2 defined NR1 compatible number, which is an integer without any decimal point (for example, 123).
@2	%d and %f only	Converts to an IEEE 488.2 defined NR2 compatible number. The NR2 number has at least one digit after the decimal point (for example, 123.45).
@3	%d and %f only	Converts to an IEEE 488.2 defined NR3 compatible number. An NR3 number is a floating point number represented in an exponential form (for example, 1.2345E67).
@H	%d and %f only	Converts to an IEEE 488.2 defined <hexadecimal numeric<br="">RESPONSE DATA>. The number is represented in a base of sixteen form. Only capital letters should represent numbers. The number is of form #HXXX, where XXX is a hexadecimal number (for example, #HAF35B).</hexadecimal>
@Q	%d and %f only	Converts to an IEEE 488.2 defined <octal numeric<br="">RESPONSE DATA>. The number is represented in a base of eight form. The number is of the form #QYYY, where YYY is an octal number (for example, #Q71234).</octal>
@B	%d and %f only	Converts to an IEEE 488.2 defined <binary numeric<br="">RESPONSE DATA>. The number is represented in a base two form. The number is of the form #BZZZ, where ZZZ is a binary number (for example, #B011101001).</binary>

The following are the allowed format code characters. A format specifier sequence should include one and only one format code.

Standard ANSI C Format Codes

% Send the ASCII percent (%) character.

c Argument type: A character to be sent.

d Argument type: An integer.

Table 84: Modifiers used with argument types %, c, and d with viPrintf()

Modifier	Interpretation
Default functionality	Print an integer in NR1 format (an integer without a decimal point).
@2 or @3	The integer is converted into a floating point number and output in the correct format.
field width	Minimum field width of the output number. Any of the six IEEE 488.2 modifiers can also be specified with field width.
Length modifier I	arg is a long integer.
Length modifier h	arg is a short integer.
, array size	arg points to an array of integers (or long or short integers, depending on the length modifier) of size array size. The elements of this array are separated by array size 1 commas and output in the specified format.

f Argument type: A floating point number.

Table 85: Modifiers used with argument type f with viPrintf()

Modifier	Interpretation
Default functionality	Print a floating point number in NR2 format (a number with at least one digit after the decimal point).
@1	Print an integer in NR1 format. The number is truncated.
@3	Print a floating point number in NR3 format (scientific notation). Precision can also be specified.
field width	Minimum field width of the output number. Any of the six IEEE 488.2 modifiers can also be specified with field width.
Length modifier I	arg is a double float.
Length modifier L	arg is a long double.
, array size	arg points to an array of floats (or doubles or long doubles, depending on the length modifier) of size array size. The elements of this array are separated by array size - 1 commas and output in the specified format.

s Argument type: A reference to a NULL-terminated string that is sent to the device without change.

Enhanced format codes

b Argument type: A location of a block of data.

Table 86: Modifiers used with argument types s and b with viPrintf()

Modifier	Interpretation
Default functionality	The data block is sent as an IEEE 488.2 <definite arbitrary="" block="" data="" length="" response="">. A count (long integer) must appear as a flag that specifies the number of elements (by default, bytes) in the block. A field width or precision modifier is not allowed with this format code.</definite>
* (asterisk)	An asterisk may be present instead of the count. In such a case, two args are used, the first of which is a long integer specifying the count of the number of elements in the data block. The second arg is a reference to the data block. The size of an element is determined by the optional length modifier (see below), and the default is byte width.
Table continued	

Table continued...

Modifier	Interpretation
Length modifier h	arg points to an array of unsigned short integers (16 bits). The count corresponds to the number of words rather than bytes. The data is swapped and padded into standard IEEE 488.2 format, if native computer representation is different
Length modifier I	arg points to an array of unsigned long integers. The count specifies the number of longwords (32 bits). Each longword data is swapped and padded into standard IEEE 488.2 format, if native computer representation is different.
Length modifier z	arg points to an array of floats. The count specifies the number of floating point numbers (32 bits). The numbers are represented in IEEE 754 format, if native computer representation is different.
Length modifier Z	arg points to an array of doubles. The count specifies the number of double floats (64 bits). The numbers will be represented in IEEE 754 format, if native computer representation is different.

B Argument type: A location of a block of data. The functionality is similar to b, except the data block is sent as an IEEE 488.2 <INDEFINITE LENGTH ARBITRARY BLOCK RESPONSE DATA>. This format involves sending an ASCII LF character with the END indicator set after the last byte of the block.

y Argument type: A location of a block of binary data.

Table 87: Modifiers used with argument types B and y	<pre>/ with viPrintf()</pre>

Modifier	Interpretation
Default functionality	The data block is sent as raw binary data. A count (long integer) must appear as a flag that specifies the number of elements (by default, bytes) in the block. A field width or precision modifier is not allowed with this format code.
* (asterisk)	An asterisk may be present instead of the count. In such a case, two args are used, the first of which is a long integer specifying the count of the number of elements in the data block. The second arg is a reference to the data block. The size of an element is determined by the optional length modifier (see below), and the default is byte width.
Length modifier h	arg points to an array of unsigned short integers (16 bits). The count corresponds to the number of words rather than bytes. If the optional !ol byte order modifier is present, the data is sent in little endian format; otherwise, the data is sent in standard IEEE 488.2 format. The data will be byte swapped and padded as appropriate if native computer representation is different.
Length modifier I	arg points to an array of unsigned long integers (32 bits). The count specifies the number of longwords rather than bytes. If the optional !ol byte order modifier is present, the data is sent in little endian format; otherwise, the data is sent in standard IEEE 488.2 format. The data will be byte swapped and padded as appropriate if native computer representation is different.
Byte order modifier !ob	Data is sent in standard IEEE 488.2 (big endian) format. This is the default behavior if neither !ob nor !ol is present.
Byte order modifier !ol	Data is sent in little endian format.

• The END indicator is not appended when LF(\n) is part of a binary data block, as with %b or %B.

• For ANSI C compatibility, VISA also supports the following conversion codes for output codes: 'i,' 'o,' 'u,' 'n,' 'x,' 'X,' 'e,' 'E,' 'g,' 'G', and 'p.' For further explanation of these conversion codes, see the ANSI C Standard.

See also

Reading and Writing Formatted Data viScanf (vi, readFmt, <arg1, arg2, ...>) viQueryf (vi, writeFmt, readFmt, <arg1, arg2, ...>)

viQueryf (vi, writeFmt, readFmt, <arg1, arg2,...>)

Usage

Writes and reads formatted data to and from a device using the optional variable-length argument list.

C format

```
ViStatus viQueryf (ViSession vi, ViConstString writeFmt, ViConstString readFmt, ...)
```

Visual basic format

Not Applicable

Parameters

Table 88: viQueryf() parameters

Name	Direction	Description	
vi	IN	Unique logical identifier to a session.	
writeFmt	IN	ViConstString describing the format of write arguments.	
readFmt	IN	ViConstString describing the format of read arguments.	
<arg1, arg2,=""></arg1,>	IN OUT	Optional argument(s) on which write and read format strings are applied.	

Return values

Table 89: viQueryf() completion codes

Completion codes	Description
VI_SUCCESS	Successfully completed the Query operation.

Table 90: viQueryf() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_IO	Could not perform read/write operation because of I/O error.
VI_ERROR_TMO	Timeout occurred before read/write operation completed.
VI_ERROR_INV_FMT	A format specifier in the writeFmt or readFmt string is invalid.
VI_ERROR_NSUP_FMT	A format specifier is not supported for current argument type.
VI_ERROR_ALLOC	The system could not allocate a formatted I/O buffer because of insufficient system resources.

C example

// Get the yoffset to help calculate the vertical values. status = viQueryf(vi, "WFMOUTPRE:YOFF?\n", "%f", &yoffset); if (status < VI SUCCESS) goto error; // Get the ymult to help calculate the vertical values. status = viQueryf(vi, "WFMOutpre:YMULT?\n", "%f", &ymult); if (status < VI SUCCESS) goto error;

Comments

This operation provides a mechanism of "Send, then Receive" typical to a command sequence from a commander device. In this manner, the response generated from the command can be read immediately.

- This operation is a combination of the viPrintf() and viScanf() operations.
- The first n arguments corresponding to the first format string are formatted by using the writeFmt string, then sent to the device. The write buffer is flushed immediately after the write portion of the operation completes. After these actions, the response data is read from the device into the remaining parameters (starting from parameter n+1) using the readFmt string.



Note: Because the prototype for this function cannot provide complete type-checking, remember that all output parameters must be passed by reference.

See also

Reading and Writing Formatted Data viPrintf (vi, writeFmt, <arg1, arg2, ...>) viScanf (vi, readFmt, <arg1, arg2, ...>)

viRead (vi, buf, count, retCount)

Usage

Reads data synchronously from a device into the specified buffer

C Format

```
ViStatus viRead (ViSession vi, ViPBuf buf, ViUInt32 count, ViPUInt32 retCount)
```

Visual basic format

viRead (ByVal vi As Long, ByVal buf As String, ByVal count As Long, ByVal retCountAs Long) As Long

Parameters

Table 91: viRead() Parameters

Name	Direction	Description	
vi	IN	Unique logical identifier to a session.	
buf	OUT	Represents the location of a buffer to receive data from device.	
count	IN	Number of bytes to be read.	
Table continued			

Table continued...

Name	Direction	Description
retCount		Represents the location of an integer that will be set to the number of bytes actually transferred.

Return values

Table 92: viRead() completion codes

Completion codes	Description
	The operation completed successfully and the END indicator was received (for interfaces that have END indicators).
VI_SUCCESS_TERM_CHAR	The specified termination character was read.
VI_SUCCESS_MAX_CNT	The number of bytes read is equal to count.

Table 93: viRead() error codes

Error codes	Description	
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).	
VI_ERROR_INV_OBJECT		
VI_ERROR_NSUP_OPER	The given vi does not support this operation.	
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because theresource identified by vi has been locked for this kind of access.	
VI_ERROR_TMO	Timeout expired before operation completed.	
VI_ERROR_RAW_WR_PROT_VIOL	Violation of raw write protocol occurred during transfer.	
VI_ERROR_RAW_RD_PROT_VIOL	Violation of raw read protocol occurred during transfer.	
VI_ERROR_OUTP_PROT_VIOL	Device reported an output protocol error during transfer.	
VI_ERROR_BERRt	Bus error occurred during transfer.	
VI_ERROR_INV_SETUP	Unable to start read operation because setup is invalid (due to attributes being set to an inconsistent state).	
VI_ERROR_NCIC	The interface associated with the given vi is not currently the controller in charge.	
VI_ERROR_NLISTENERS	No Listeners condition is detected (both NRFD and NDAC are deasserted).	
VI_ERROR_ASRL_PARITY	A parity error occurred during transfer.	
VI_ERROR_ASRL_FRAMING A framing error occurred during transfer.		
VI_ERROR_ASRL_OVERRUN	An overrun error occurred during transfer. A character was not read from the hardware before the next character arrived.	
VI_ERROR_IO	An unknown I/O error occurred during transfer.	

C example

if (viWrite(vi, (ViBuf) "*idn?", 5, VI_NULL) < VI_SUCCESS) return; if (viRead(vi, (ViBuf), buffer, sizeof(buffer)--1, &retCnt) < VI_SUCCESS) return; buffer[retCnt] = '\0'; // ensures null terminator in string

Comments

The viRead() operation synchronously transfers data. The data read is to be stored in the buffer represented by buf. This operation returns only when the transfer terminates. Only one synchronous read operation can occur at any one time.

- A viRead() operation can complete successfully if one or more of the following conditions were met (it is possible to have one, two, or all three ofnthese conditions satisfied at the same time):
 - END indicator received.
 - · Termination character read.
 - Number of bytes read is equal to count.

Condition 1: End indicator received

- If the following conditions are met, viRead() returns VI_SUCCESS regardless of whether the termination character is received or the number of bytes read is equal to count.
 - If an END indicator is received, and
 - VI_ATTR_SUPPRESS_END_EN is VI_FALSE.
- If either of the following conditions are met, viRead() will not terminate because of an END condition (and therefore will not return VI_SUCCESS). The operation can still complete successfully due to a termination character or reading the maximum number of bytes requested.
 - If VI_ATTR_SUPPRESS_END_EN is VI_TRUE
 - If vi is a session to an ASRL INSTR resource, and VI_ATTR_ASRL_END_IN is VI_ASRL_END_NONE.

Condition 2: Termination character read

- If the following conditions are met, viRead() returns VI_SUCCESS_TERM_CHAR regardless of whether the number of bytes read is
 equal to count.
 - If no END indicator is received, and
 - the termination character is read, and
 - VI_ATTR_TERMCHAR_EN is VI_TRUE.
- Under the following condition, viRead() will not terminate because of reading a termination character (and therefore will not return VI_SUCCESS_TERM_CHAR). The operation can still complete successfully due to reading the maximum number of bytes requested.
 - If VI_ATTR_TERMCHAR_EN is VI_FALSE.
- If the following conditions are met, viRead() treats the value stored inVI_ATTR_TERMCHAR as an END indicator regardless of the value of VI_ATTR_TERMCHAR_EN.
 - · If vi is a session to an ASRL INSTR resource, and
 - VI_ATTR_ASRL_END_IN is VI_ASRL_END_TERMCHAR.

Condition 3: Number of Bytes Read Equals Count

- If the following conditions are met, viRead() returns VI_SUCCESS_MAX_CNT.
 - · If no END indicator is received, and
 - no termination character is read, and
 - the number of bytes read is equal to count.
- If you pass VI_NULL as the retCount parameter to the viRead() operation, the number of bytes transferred will not be returned. This
 may be useful if it is only important to know whether the operation succeeded or failed.

Table 94: Success code conditions for GPIB interfaces with ViRead()

TRUE	FALSE	Success Code
END received	VI_ATTR_SUPPRESS_END_EN	VI_SUCCESS
VI_ATTR_TERM_CHAR_EN	END received	VI_SUCCESS_TERM_CHAR
max bytes requested received	END received	VI_SUCCESS_TERM_CHAR

See also

Reading and Writing Data viWrite (vi, buf, count, retCount)

viReadAsync (vi, buf, count, jobld)

Usage

Reads data synchronously from a device into the specified buffer

C format

ViStatus viReadAsync (ViSession vi, ViPBuf buf, ViUInt32 count, ViPJobId jobId)

Visual basic format

Not Applicable

Parameters

Table 95: viReadAsync() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
buf	OUT	Represents the location of a buffer to receive data from device.
count	IN	Number of bytes to be read.
jobld	OUT	Represents the location of a variable that will be set to the job identifier of this asynchronous read operation.

Return values

Table 96: viReadAsync() completion codes

Completion codes	Description
VI_SUCCESS	Asynchronous read operation successfully queued.
VI_SUCCESS_SYNC	Read operation performed synchronously.

Table 97: viReadAsync() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because theresource identified by vi has been locked for this kind of access.
VI_ERROR_QUEUE_ERROR	Unable to queue read operation.

C example

```
// rwwait.cpp
//
#include <stdio.h>
#include <string.h>
#include <windows.h>
#include "visa.h"
// viReadAsync/viWriteAsync example --
// These commands can potentially decrease test time by allowing
// several read or write commands to happen in parallel.
int main(int argc, char* argv[]){
ViSession rm, vi[2];
ViJobId jobid[2];
ViStatus status;
char string[2][256];
ViEventType eventType[2];
ViEvent event[2];
int i;
// clear strings
for (i = 0; i < 2; i++) {
memset(string[i], 0, 256);
}
// Open the default RM
status = viOpenDefaultRM(&rm);
if (status < VI_SUCCESS) goto error;
// Open multiple devices
status = viOpen(rm, "GPIB0::1::INSTR", NULL, NULL, &vi[0]);
if (status < VI SUCCESS) goto error;
status = viOpen(rm, "GPIB8::1::INSTR", NULL, NULL,
&vi[1]);
if (status < VI SUCCESS) goto error;
// Enable waiting on the events
for (i = 0; i < 2; i++)
status = viEnableEvent(vi[i], VI EVENT IO COMPLETION,
VI QUEUE, VI NULL);
if (status < VI SUCCESS) goto error;
ł
// Write commands to several devices (this allows
// several writes to be done in parallel)
for (i = 0; i < 2; i++)
status = viWriteAsync(vi[i],(ViBuf) "*idn?",
```

```
5, &jobid[i]);
if (status < VI SUCCESS) goto error;
}
// Wait for completion on all of the devices
for (i = 0; i < 2; i++) {
viWaitOnEvent(vi[i], VI EVENT IO COMPLETION,
INFINITE, &eventType[i], &event[i]);
}
// Queue the read for all the devices (this allows
// several reads to be done im parallel)
for (i = 0; i < 2; i++) {
status = viReadAsync(vi[i], (ViBuf) string[i],
256, &jobid[i]);
if (status < VI SUCCESS) goto error;
}
// Wait for all the reads to complete
for (i = 0; i < 2; i++) {
viWaitOnEvent(vi[i], VI EVENT IO COMPLETION,
INFINITE, &eventType[i], &event[i]);
// Write out the *idn? strings.
for (i = 0; i < 2; i++) {
printf("%d: %s\n", i, string[i]);
ł
// Cleanup and exit
for (i = 0; i < 2; i++)
status = viDisableEvent(vi[i], VI EVENT IO COMPLETION,
VI QUEUE);
if (status < VI SUCCESS) goto error;
}
viClose(rm);
return 0;
error:
viStatusDesc(rm, status, string[0]);
fprintf(stderr, "Error: %s\n", (ViBuf) string[0]);
return 0;
}
```

Comments

The viReadAsync() operation asynchronously transfers data. The data read is to be stored in the buffer represented by buf. This operation normally returns before the transfer terminates.

- Before calling this operation, you should enable the session for receiving I/O completion events. After the transfer has completed, an I/O completion event is posted.
- The operation returns jobId, which you can use either
 - with viTerminate() to abort the operation, or
 - with an I/O completion event to identify which asynchronous read operation completed.

Table 98: Special value for jobId parameter with viReadAsync()

Value	Description
	Do not return a job identifier. This option may be useful if only one asynchronous operation will be pending at a given time.

- Since an asynchronous I/O request could complete before viReadAsync() returns, and the I/O completion event can be distinguished based on the job identifier, an application must be made aware of the job ID before the first moment that the I/O completion event could possibly occur. Setting jobId before the data transfer even begins ensures that an application can always match the jobId with the VI_ATTR_JOB_ID attribute of the I/O completion event.
- If multiple jobs are queued at the same time on the same session, an application can use the jobId to distinguish the jobs, as they are unique within a session.
- The viReadAsync() operation may be implemented synchronously, which could be done by using the viRead() operation. This means that an application can use the asynchronous operations transparently, even if a low-level driver supports only synchronous data transfers. If viReadAsync() is implemented synchronously and a given invocation is valid, it returns VI_SUCCESS_SYNC and all status information is returned in a VI_EVENT_IO_COMPLETION. Status codes are the same as those listed for viRead().
- The status code VI_ERROR_RSRC_LOCKED can be returned either immediately or from the VI_EVENT_IO_COMPLETION event.
- The contents of the output buffer pointed to by buf are not guaranteed to be valid until the VI_EVENT_IO_COMPLETION event occurs.
- For each successful call to viReadAsync(), there is one and only one VI_EVENT_IO_COMPLETION event occurrence.
- If the jobId parameter returned from viReadAsync() is passed to viTerminate() and a VI_EVENT_IO_COMPLETION event has not yet
 occurred for the specified jobId, the viTerminate() operation raises a VI_EVENT_IO_COMPLETION event on the given vi, and the
 VI_ATTR_STATUS field of that event is set to VI_ERROR_ABORT.

See also

Asynchronous Read/Write viWriteAsync (vi, buf, count, jobld) viTerminate (vi, degree, jobld)

viReadSTB (vi, status)

Usage

Reads a status byte of the service request.

C format

ViStatus viReadSTB (ViSession vi, ViPUInt16 status)

Visual basic format

viReadSTB (ByVal vi As Long, ByVal status As Integer) As Long

Parameters

Table 99: viReadSTB() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
status	OUT	Service request status byte.

Return values

Table 100: viReadSTB() completion codes

Completion codes	Description
VI_SUCCESS	Operation completed successfully.

Table 101: viReadSTB() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is not valid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_NSUP_OPER	The given vi does not support this operation.
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_SRQ_NOCCURRED	Service request has not been received for the session.
VI_ERROR_TMO	Timeout expired before operation completed.
VI_ERROR_RAW_WR_PROT_VIOL	Violation of raw write protocol occurred during transfer.
VI_ERROR_RAW_RD_PROT_VIOL	Violation of raw read protocol occurred during transfer.
VI_ERROR_BERR	Bus error occurred during transfer.
VI_ERROR_NCIC	The interface associated with the given vi is not currently the controller in charge.
VI_ERROR_NLISTENERS	No Listeners condition is detected (both NRFD and NDAC are deasserted).
VI_ERROR_INV_SETUP	Unable to start read operation because setup is invalid (due to attributes being set to an inconsistent state).

C example

ViUInt16 stb; viReadSTB(vi, &stb);

Comments

The viReadSTB() operation reads a service request status from a service requester (the message-based device). For example, on the IEEE 488.2 interface, the message is read by polling devices; for other types of interfaces, a message is sent in response to a service request to retrieve status information.

- For a serial device, if VI_ATTR_IO_PROT is VI_ASRL488, the device is sent the string "*STB?\n", and then the device's status byte is read.
- This operation is not valid for a serial device if VI_ATTR_IO_PROT is VI_NORMAL. In that case, viReadSTB() returns VI_ERROR_INV_SETUP.
- If the status information is only one byte long, the most significant byte is returned with the zero value.
- If the service requester does not respond in the actual timeout period, VI_ERROR_TMO is returned.

See also

Status/Service Request

VI_ATTR_IO_PROT

viReadToFile (vi, fileName, count, retCount)

Usage

Reads data synchronously from a device, and stores the transferred data in a file.

C format

```
ViStatus viReadToFile (ViSession vi, ViString fileName, ViUInt32 count, ViUInt32retCount)
```

Visual basic format

viReadToFile(By Val vi As Long, By Val fileNameAs String, By Val count As Long, By Val retCount As Long) As Long

Parameters

Table 102: viReadToFile() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
fileName	IN	Name of the file to which data will be written.
count	IN	Number of bytes to be read.
retCount	OUT	Number of bytes actually transferred.

Return values

Table 103: viReadToFile() completion codes

Completion codes	Description
VI_SUCCESS	The operation completed successfully and the END indicator was received (for interfaces that have END indicators).
VI_SUCCESS_TERM_CHAR	The specified termination character was read.
VI_SUCCESS_MAX_CNT	The number of bytes read is equal to count.

Table 104: viReadToFile() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is not valid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_NSUP_OPER	The given vi does not support this operation.
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_TMO	Timeout expired before operation completed.
Table continued	

Table continued...

Error codes	Description
VI_ERROR_RAW_WR_PROT_VIOL	Violation of raw write protocol occurred during transfer.
VI_ERROR_RAW_RD_PROT_VIOL	Violation of raw read protocol occurred during transfer.
VI_ERROR_OUTP_PROT_VIOL	Device reported an output protocol error during transfer.
VI_ERROR_BERR	Bus error occurred during transfer.
VI_ERROR_INV_SETUP	Unable to start read operation because setup is not valid (due to attributes being set to an inconsistent state).
VI_ERROR_NLISTENERS	No listeners condition is detected (both NRFD and NDAC are deasserted).
VI_ERROR_ASRL_PARITY	A parity error occurred during transfer.
VI_ERROR_ASRL_FRAMING	A framing error occurred during transfer.
VI_ERROR_ASRL_OVERRUN	An overrun error occurred during transfer. A character was not read from the hardware before the next character arrived.
VI_ERROR_IO	An unknown I/O error occurred during transfer.
VI_ERROR_FILE_ACCESS	An error occurred while trying to open the specified file. Possible reasons include an not valid path or lack of access right.
VI_ERROR_FILE_IO	An error occurred while accessing the specified file.
VI_ERROR_CONN_LOST	The I/O connection for the given session has been lost.

C example

```
ViSession rm, vi;
ViStatus status = VI_SUCCESS;
ViUInt32 retCount;
if (viOpenDefaultRM(&rm) < VI_SUCCESS) return;
if (viOpen(rm, "GPIB8::1::INSTR", NULL, NULL, &vi) < VI_SUCCESS)
return;
status = viReadToFile(vi,"curve.bin",20,&retCount);
viClose(vi);
viClose(rm);
```

Comments

This read operation synchronously transfers data. The file specified in fileName is opened in binary write-only mode. If the value of VI_ATTR_FILE_APPEND_EN is VI_FALSE, any existing contents are destroyed; otherwise, the file contents are preserved. The data read is written to the file. This operation returns only when the transfer terminates.

This operation is useful for storing raw data to be processed later.

Table 105: Special value for the retCount parameter with viReadToFile()

Error codes	Description
VI_NULL	Do not return the number of bytes transferred.

See also

```
Reading and Writing Data viRead (vi, buf, count, retCount)
```

viWriteFromFile (vi, fileName, count, retCount)

viScanf (vi, readFmt, <arg1, arg2,...>)

Usage

Reads and formats data from a device using the optional variable-length argument list.

C format

ViStatus viScanf (ViSession vi, ViConstString readFmt, ...)

Visual basic format

Not Applicable

Parameters

Table 106: viScanf() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
readFmt	IN	String describing the format for arguments.
<arg1, arg2,=""></arg1,>	OUT	Optional arguments into which the data is read and the format string is applied.

Return values

Table 107: viScanf() completion codes

Completion codes	Description
VI_SUCCESS	Data is successfully read and formatted into arg parameters

Table 108: viScanf() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is not valid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_IO	Could not perform read operation because of I/O error.
VI_ERROR_TMO	Timeout expired before read operation completed.
VI_ERROR_INV_FMT	A format specifier in the readFmt string is not valid.
VI_ERROR_NSUP_FMT	A format specifier in the readFmt string is not supported.
VI_ERROR_ALLOC	The system could not allocate a formatted I/O buffer because of insufficient system resources.

C example

```
// Get first char and validate
status = viScanf(vi, "%c", &c);
if (status < VI SUCCESS) goto error;
assert(c == '#');
// Get width of element field.
status = viScanf(vi, "%c", &c);
if (status < VI SUCCESS) goto error;
assert(c >= '0' && c <= '9');
// Read element characters
\operatorname{count} = \operatorname{c} - \operatorname{'0'};
for (i = 0; i < \text{count}; i^{++})
status = viScanf(vi, "%c", &c);
if (status < VI SUCCESS) goto error;
assert(c >= '0' && c <= '9');
// Read waveform into allocated storage
ptr = (double*) malloc(*elements*sizeof(double));
for (i = 0; i < \text{*elements}; i++)
status = viScanf(vi, "%c", &c);
if (status < VI SUCCESS) goto error;
ptr[i] = (((double) c) -- yoffset) * ymult;
ł
return ptr;
```

Comments

The viScanf() operation receives data from a device, formats it by using the format string, and stores the resulting data in the arg parameter list. This operation is useful for storing raw data to be processed later.

The viRead() operation is used for the actual low-level read from the device. As a result, you should not use the viRead() and viScanf() operations in the same session.



Note: Because the prototype for this function cannot provide complete type-checking, remember that all output parameters must be passed by reference.

- · The format string can have format specifier sequences, white characters, and ordinary characters.
 - The white characters—blank, vertical tabs, horizontal tabs, form feeds, new line/linefeed, and carriage return—are ignored except in the case of %c and %[].
 - · All other ordinary characters except % should match the next character read from the device.
- The format string consists of a %, followed by optional modifier flags, followed by one of the format codes in that sequence. It is of the form %[modifier]format code
 - · where the optional modifier describes the data format,
 - while format code indicates the nature of data (data type).
- One and only one format code should be performed at the specifier sequence. A format specification directs the conversion to the
 next input arg. The results of the conversion are placed in the variable that the corresponding argument points to, unless the *
 assignment-suppressing character is given. In such a case, no arg is used and the results are ignored.
- The viScanf() operation accepts input until an END indicator is read or all the format specifiers in the readFmt string are satisfied. Thus, detecting an END indicator before the readFmt string is fully consumed will result in ignoring the rest of the format string. Also, if some data remains in the buffer after all format specifiers in the readFmt string are satisfied, the data will be kept in the buffer and will be used by the next viScanf() operation.

• When viScanf() times out, the next call to viScanf() will read from an empty buffer and force a read from the device. Notice that when an END indicator is received, not all arguments in the format string may be consumed. However, the operation still returns a successful completion code. The following two tables describe optional modifiers that can be used in a format specifier sequence.

ANSI C standard modifiers

Table 109: ANSI C standard modifiers used with viScanf()

Modifier	Supported with format code	Description	
An integer specifying field width.	%s, %c, %[] format codes	It specifies the maximum field width that the argument will take. A '#' may also appear instead of the integer field width, in which case the next arg is a reference to the field width. This arg is a reference to an integer for %c and %s. The field width is not allower for %d or %f.	
A length modifier ('h,' 'l,' 'L,' 'z,' or 'Z'). z and Z are not ANSI C standard modifiers.	h (d, b format codes) I (d, f, b format codes) L (f format code) z (b format code) Z (b	The argument length modifiers specify one of the following:	
	format code)	• The h modifier promotes the argument to be a reference to a short integer or unsigned short integer, depending on the format code.	
		• The I modifier promotes the argument to point to a long integer or unsigned long integer.	
		• The L modifier promotes the argument to point to a long double floats parameter.	
		• The z modifier promotes the argument to point to an array of floats.	
		• The Z modifier promotes the argument to point to an array of double floats.	
*	All format codes	An asterisk (*) acts as the assignment suppression character. The input is not assigned to any parameters and is discarded.	

Enhanced modifiers to ANSI C standards

Table 110: Enhanced modifiers to ANSI C standards used with viScanf()

Modifier	Supported with format	Code description
A comma (,) followed by an integer n, where n represents the array size.	%d and %f only	The corresponding argument is interpreted as a reference to the first element of an array of size n. The first n elements of this list are printed in the format specified by the format code. A number sign (#) may be present after the comma (,) modifier, in which case an extra arg is used. This arg must be an integer representing the array size of the given type.

Format codes

ANSI C format codes

c Argument type: A reference to a character.

Table 111: Modifiers used with argument type c with viScanf()

Modifier	Interpretation	
	A character is read from the device and stored in the parameter. field width field width number of characters are read and stored at the reference location (the default field width is 1). No NULL character is added at the end of the data block.	



Note: This format code does not ignore white space in the device input stream.

d Argument type: A reference to an integer.

Table 112: Modifiers used with argument type d with viScanf()

Modifier	Interpretation
Default functionality	Characters are read from the device until an entire number is read. The number read may be in either IEEE 488.2 formats <decimal data="" numeric="" program="">, also known as NRf; flexible numeric representation (NR1, NR2, NR3); or <non-decimal data="" numeric="" program=""> (#H, #Q, and #B).</non-decimal></decimal>
field width	The input number will be stored in a field at least this wide.
Length modifier I	arg is a reference to a long integer.
Length modifier h	arg is a reference to a short integer. Rounding is performed according to IEEE 488.2 rules (0.5 and up).
, array size	arg points to an array of integers (or long or short integers, depending on the length modifier) of size array size. The elements of this array should be separated by commas. Elements will be read until either array size number of elements are consumed or they are no longer separated by commas.

s Argument type: A reference to a string.

Table 113: Modifiers used with argument type s with viScanf()

Modifier	Interpretation
Default functionality	All leading white space characters are ignored. Characters are read from the device into the string until a white space character is read.
field width	This flag gives the maximum string size. If the field width contains a number sign (#), two arguments are used. The first argument read is a pointer to an integer specifying the maximum array size. The second should be a reference to an array. In case of field width characters already read before encountering a white space, additional characters are read and discarded until a white space character is found. In case of # field width, the actual number of characters read are stored back in the integer pointed to by the first argument.

Enhanced format codes

bArgument type: A reference to a data array.

Table 444.	Ma differen			4		· · · · f()
Table 114:	woattiers	usea with	argument	type t) with visc	cant()

Modifier	Interpretation		
Default functionality	The data must be in IEEE 488.2 <arbitrary block="" data="" program="">format. The format specifier sequence should have a flag describing the field width, which will give a maximum count of the number of bytes (or words or longwords, depending on length modifiers) to be read from the device. If the field width contains a # sign, two arguments are used. The first arg read is a pointer to a long integer specifying the maximum number of elements that the array can hold. The second arg should be a reference to an array. Also, the actual number of elements read is stored back in the first argument. In the absence of length modifiers, the data is assumed to be of byte-size elements. In some cases, data might be read until an END indicator is read.</arbitrary>		
Length modifier h	arg points to an array of 16-bit words, and count specifies the number of words. Data that is read is assumed to be in IEEE 488.2 byte ordering. It will be byte swapped and padded as appropriate to native computer format.		
Length modifier I	arg points to an array of 32-bit longwords, and count specifies the number of longwords. Data that is read is assumed to be in IEEE 488.2 byte ordering. It will be byte swapped and padded as appropriate to native computer format.		
Length modifier z	arg points to an array of floats, and count specifies the number of floating point numbers. Data that is read is an array of 32-bit IEEE 754 format floating point numbers.		
Length modifierZ	arg is a reference to a long double number.		
, array size	arg points to an array of doubles, and the count specifies the number of floating point numbers. Data that is read is an array of 64-bit IEEE 754 format floating point numbers.		

t Argument type: A reference to a string.

Table 115: Modifiers used with argument type t with viScanf()

Modifier	Interpretation
Default functionality	Characters are read from the device until the first END indicator is received. The character on which the END indicator was received is included in the buffer.
field width	This flag gives the maximum string size. If an END indicator is not received before field width number of characters, additional characters are read and discarded until an END indicator arrives. #field width has the same meaning as in %s.

T Argument type: A reference to a string.

Table 116: Modifiers used with argument type T with viScanf()

Modifier	Interpretation
-	Characters are read from the device until the first linefeed character (\n) is received. The linefeed character is included in the buffer.
	This flag gives the maximum string size. If a linefeed character is not received before field width number of characters, additional characters are read and discarded until a linefeed character arrives. #field width has the same meaning as in %s.

y Argument type: A location of a block of binary data.

Modifier	Interpretation
Default functionality	The data block is read as raw binary data. The format specifier sequence should have a flag describing the array size, which will give a maximum count of the number of bytes (or words or longwords, depending on length modifiers) to be read from the device. If the array size contains a # sign, two arguments are used. The first argument read is a pointer to a long integer that specifies the maximum number of elements that the array can hold. The second argument should be a reference to an array. Also, the actual number of elements read is stored back in the first argument. In the absence of length modifiers, the data is assumed to be byte-size elements. In some cases, data might be read until an END indicator is read.
Length modifier h	The data block is assumed to be a reference to an array of unsigned short integers (16 bits). The count corresponds to the number of words rather than bytes. If the optional "!ol" modifier is present, the data read is assumed to be in little endian format; otherwise, the data read is assumed to be in standard IEEE 488.2 format. The data will be byte swapped and padded as appropriate to native computer format.
Length modifier I	The data block is assumed to be a reference to an array of unsigned long integers (32 bits). The count corresponds to the number of longwords rather than bytes. If the optional "!ol" modifier is present, the data read is assumed to be in little endian format; otherwise, the data read is assumed to be in standard IEEE 488.2 format. The data will be byte swapped and padded as appropriate to native computer format.
Byte order modifier!ob	The data being read is assumed to be in standard IEEE 488.2 (big endian) format. This is the default behavior if neither !ob nor !ol is present.
Byte order modifier !ol	The data being read is assumed to be in little endian format.

Table 117: Modifiers used with argument type y with viScanf()

 For ANSI C compatibility, VISA also supports the following conversion codes for input codes: 'i,' 'o,' 'u,' 'n,' 'x,' 'X,' 'e,' 'E,' 'g,' 'G,' 'p,' ' [...],' and '[^...].' For further explanation of these conversion codes, see the ANSI C Standard.

See also

Reading and Writing Formatted Data viPrintf (vi, writeFmt, <arg1, arg2, ...>) viQueryf (vi, writeFmt, readFmt, <arg1, arg2, ...>) VI_ATTR_RD_BUF_OPER_MODE

viSetAttribute (vi, attribute, attrState)

Usage

Sets the state of an attribute for the specified session, event, or find list.

C format

ViStatus viSetAttribute(ViObject vi, ViAttr attribute, ViAttrState attrState)

Visual Basic Format

viSetAttribute (ByVal vi As Long, ByVal attribute As Long, ByVal attrState As Long)As Long

Parameters

Table 118: viScanf() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
attribute	IN	Attribute for which the state is to be modified.
attrState	IN	The state of the attribute to be set for the specified resource. The interpretation of the individual attribute value is defined by the resource.

Return values

Table 119: viScanf() completion codes

Completion codes	Description
VI_SUCCESS	Attribute value set successfully.
VI_WARN_NSUP_ATTR_STATE	Although the specified attribute state is valid, it is not supported by this implementation.

Table 120: viSetAttribute() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is not valid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_NSUP_ATTR	The specified attribute is not defined by the referenced session, event, or find list.
VI_ERROR_NSUP_ATTR_STATE	The specified state of the attribute is not valid, or is not supported as defined by the session, event, or find list
VI_ERROR_ATTR_READONLY	The specified attribute is read-only.

C example

// Set timeout to 5 seconds
status = viSetAttribute(vi, VI_ATTR_TMO_VALUE, 5000);
if (status < VI_SUCCESS) goto error;</pre>

Comments

The viSetAttribute() operation is used to modify the state of an attribute for the specified object.

- Both VI_WARN_NSUP_ATTR_STATE and VI_ERROR_NSUP_ATTR_STATE indicate that the specified attribute state is not supported.
 - A resource normally returns the error code VI_ERROR_NSUP_ATTR_STATE when it cannot set a specified attribute state.
 - The completion code VI_WARN_NSUP_ATTR_STATE is intended to alert the application that although the specified optional
 attribute state is not supported, the application should not fail. One example is attempting to set an attribute value that would
 increase performance speeds. This is different from attempting to set an attribute value that specifies required but nonexistent
 hardware, or a value that would change assumptions a resource might make about the way data is stored or formatted (such as
 byte order)

See also

Setting and Retrieving Attributes viGetAttribute (vi, attribute, attrState)

viSetBuf (vi, mask, size)

Usage

Sets the size of the formatted I/O and/or serial buffers.

C format

ViStatus viSetBuf(ViSession vi, ViUInt16 mask, ViUInt32 size)

Visual basic format

viSetBuf (ByVal vi As Long, ByVal mask As Integer, ByVal size As Long) As Long

Parameters

Table 121: viSetBuf() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
mask	IN	Specifies the type of buffer.
size	IN	The size to be set for the specified buffer(s)

Return values

Table 122: viSetBuf() completion codes

Completion codes	Description
VI_SUCCESS	Buffer size set successfully.
VI_WARN_NSUP_BUF	The specified buffer is not supported.

Table 123: viSetBuf() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is not valid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_ALLOC	The system could not allocate the buffers of the specified size because of insufficient system resources.
VI_ERROR_INV_MASK	The system cannot set the buffer for the given mask.

C example

```
viSetBuf(vi, VI READ BUF, 1024*10); // set buffer to 10K
```

Comments

The viSetBuf() operation changes the buffer size of the read and/or write buffer for formatted I/O and/or serial communication. The mask parameter specifies the buffer for which to set the size. The mask parameter can specify multiple buffers by bit-ORing any of the following values together.

Table 124: Flags used with mask parameter with viSetBuf()

Flag	Interpretation
VI_READ_BUF	Formatted I/O read buffer.
VI_WRITE_BUF	Formatted I/O write buffer.
VI_ASRL_IN_BUF	Serial communication receive buffer.
VI_ASRL_OUT_BUF	Serial communication transmit buffer.

- A call to viSetBuf() flushes the session's related read/write buffer). Although you can explicitly flush the buffers by making a call to • viFlush(), the buffers are flushed implicitly under some conditions. These conditions vary for the viPrintf() and viScanf() operations.
- Since not all serial drivers support user-defined buffer sizes, VISA may not be able to control this feature. If an application requires a specific buffer size for performance reasons, but VISA cannot guarantee that size, we recommend you use some form of handshaking to prevent overflow conditions.

See also

Reading and Writing Formatted Data viFlush (vi, mask)

viSPrintf (vi, buf, writeFmt, <arg1, arg2,...>)

Usage

Formats and writes data to a user-specified buffer using an optional variable-length argument list.

C format

```
ViStatus viSPrintf (ViSession vi, ViPBuf buf, ViConstString writeFmt, ...)
```

Visual basic format

Not Applicable

Parameters

Table 125: viSPrintf() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
Table continued		

[lable continued...

Name	Direction	Description
buf	OUT	Buffer where data is to be written.
writeFmt	IN	The format string to apply to arguments.
<arg1,arg2,></arg1,arg2,>		Optional arguments on which the format string is applied. The formatted data is written to the specified buffer.

Return values

Table 126: viSPrintf() completion codes

Completion codes	Description
VI_SUCCESS	Parameters were successfully formatted.

Table 127: viSPrintf() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is not valid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_INV_FMT	A format specifier in the writeFmt string is not valid.
VI_ERROR_NSUP_FMT	A format specifier in the writeFmt string is not supported.
VI_ERROR_ALLOC	The system could not allocate a formatted I/O buffer because of insufficient system resources.

C example

```
#include <stdio.h>
#include <string.h>
#include <visa.h>
#include <stdarg.h>
// This example opens a specific GPIB device, sets the data start
// and stop locations and logs the command sent to c:\logfile.txt
int main(int argc, char* argv[])
{
ViSession rm = VI_NULL, vi = VI_NULL;
ViStatus status;
ViChar buffer[256];
const long start = 1;
const long stop = 500;
FILE* log = fopen("C:\\logfile.txt", "w");
// Open a default Session
status = viOpenDefaultRM(&rm);
if (status < VI SUCCESS) goto error;
// Open the gpib device at primary address 1, gpib board 8
status = viOpen(rm, "GPIB0::1::INSTR", VI_NULL, VI_NULL,
&vi);
if (status < VI SUCCESS) goto error;
status = viSPrintf(vi, (ViBuf) buffer, "data:start %d;
```

data:stop %d", start, stop);

```
if (status < VI_SUCCESS) goto error;
if (log != NULL)
fprintf(log, "%s'n", buffer);
status = viWrite(vi, (ViBuf) buffer, strlen(buffer),
VI NULL);
if (status < VI_SUCCESS) goto error;
// Clean up
if (log != NULL)
fclose(log);
viClose(vi); // Not needed, but makes things a bit more
// understandable
viClose(rm):
return 0;
error:
// Report error and clean up
viStatusDesc(vi, status, buffer);
fprintf(stderr, "failure: %s\n", buffer);
if (rm != VI NULL) {
viClose(rm);
}
return 1;
}
```

Comments

The viSPrintf() operation is similar to viPrintf(), except that the output is not written to the device; it is written to the user-specified buffer. This output buffer will be NULL terminated.

If this operation outputs an END indicator before all the arguments are satisfied, the rest of the writeFmt string is ignored and the buffer string is still terminated by a NULL.

See also

```
Reading and Writing Formatted Data
viSScanf (vi, readFmt, <arg1, arg2,...>)
```

viSScanf (vi, buf, readFmt, <arg1, arg2,...>)

Usage

Reads and formats data from a user-specified buffer using an optional variable-length argument list.

C format

ViStatus viSScanf (ViSession vi, ViConstBuf buf, ViConstString readFmt, ...)

Visual basic format

Not Applicable

Parameters

Table 128: viSScanf() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
readFmt	IN	String describing the format for arguments.
<arg1,arg2,></arg1,arg2,>	OUT	Optional arguments into which the data is read and to which the format string is applied.

Return values

Table 129: viSScanf() completion codes

Completion codes	Description
VI_SUCCESS	Data is successfully read and formatted into arg parameters.

Table 130: viSScanf() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is not valid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_IO	Could not perform read operation because of I/O error.
VI_ERROR_TMO	Timeout expired before read operation completed.
VI_ERROR_INV_FMT	A format specifier in the readFmt string is not valid.
VI_ERROR_NSUP_FMT	A format specifier in the readFmt string is not supported.
VI_ERROR_ALLOC	The system could not allocate a formatted I/O buffer because of insufficient system resources.

C example

```
#include <stdio.h>
#include <string.h>
#include <visa.h>
#include <stdarg.h>
// This example opens a specific GPIB device, and scans
// 10 comma--separated integers into a long array
int main(int argc, char* argv[])
ł
ViSession rm = VI_NULL, vi = VI_NULL;
ViStatus status;
char buffer[256];
long scanArray[10];
ViChar *scanStr = "0,1,2,3,4,5,6,7,8,9";
int i;
// Open a default Session
status = viOpenDefaultRM(&rm);
if (status < VI_SUCCESS) goto error;
```

```
// Open the gpib device at primary address 1, gpib board 8
status = viOpen(rm, "GPIB0::1::INSTR", VI NULL, VI NULL,
&vi);
if (status < VI SUCCESS) goto error;
// Read a 10--element comma--separated array into a long array
status = viSScanf(vi, (ViBuf) scanStr, "%,10d", scanArray);
if (status < VI SUCCESS) goto error;
for (i = 0; i < 10; i++)
printf("%d ", scanArray[i]);
}
printf("\n");
viClose(vi); // Not needed, but makes things a bit more
// understandable
viClose(rm);
return 0;
error:
// Report error and clean up
viStatusDesc(vi, status, buffer);
fprintf(stderr, "failure: %s\n", buffer);
if (rm != VI NULL) {
viClose(rm);
}
return 1;
}
```

Comments

The viSScanf() operation is similar to viScanf(), except that the data is read from a user-specified buffer rather than from a device.

See also

Reading and Writing Formatted Data viSPrintf (vi, buf, writeFmt, <arg1, arg2,...>)

viStatusDesc (vi, status, desc)

Usage

Retrieves a user-readable description of the specified status code.

C format

ViStatus viStatusDesc (ViObject vi, ViStatus status, ViString desc)

Visual basic format

viStatusDesc (ByVal vi As Long, ByVal statusAs Long, ByVal desc As String) As Long

Parameters

Table 131: viStatusDesc() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session, event, or find list.
status	IN	Status code to interpret.
desc	OUT	The user-readable string interpretation of the status code passed to the operation.

Return values

Table 132: viStatusDesc() completion codes

Completion codes	Description
VI_SUCCESS	Description successfully returned.
VI_WARN_UNKNOWN_STATUS	The status code passed to the operation could not be interpreted.

C example

// Report error
viStatusDesc(vi, status, buffer);
fprintf(stderr, "failure: %s\n", buffer);

Comments

The viStatusDesc() operation is used to retrieve a user-readable string that describes the status code presented.

If the string cannot be interpreted, the operation returns the warning code VI_WARN_UNKNOWN_STATUS. However, the output string desc is valid regardless of the status return value.



Note: The size of the desc parameter should be at least 256 bytes.

See also

Appendix B: Completion and Error Codes

viTerminate (vi, degree, jobld)

Usage

Terminates normal execution of an asynchronous read or write operation.

C format

ViStatus viTerminate(ViObject vi, ViUInt16 degree,ViJobId jobId)

Visual basic format

Not Applicable

Parameters

Table 133: viTerminate() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to an object.
degree	IN	VI_NULL
jobld	IN	Specifies an operation identifier.

Return values

Table 134: viTerminate() completion codes

Completion codes	Description
VI_SUCCESS	Request serviced successfully.

Table 135: viTerminate() error codes

Error codes	Description
VI_ERROR_INV_SESSION VI_ERROR_INV_OBJECT	The given session or object reference is not valid (both are the same value).
VI_ERROR_INV_JOB_ID	Specified job identifier is not valid. This message is returned If the operation associated with the specified jobId has already completed.
VI_ERROR_INV_DEGREE	Specified degree is not valid.

C example

viTerminate(vi, VI NULL, jobid);

Comments

The vi Terminate() operation is used to request a session to terminate normal execution of an operation, as specified by the jobId parameter:

- The jobId parameter is a unique value generated from each call to an asynchronous operation.
- If a user passes VI_NULL as the jobId value to viTerminate(), VISA aborts the specified asynchronous operation and the resulting I/O completion event contains the status code VI_ERROR_ABORT.

See also

Asynchronous Read/Write viReadAsync (vi, buf, count, jobld) viWriteAsync (vi, buf, count, jobld)

viUninstallHandler (vi, eventType, handler, userHandle)

Usage

Uninstalls callback handlers for the specified event.

C format

```
ViStatus viUninstallHandler (ViSession vi, ViEventType eventType, ViHndlr handler, ViAddr userHandle)
```

Visual basic format

Not Applicable

Parameters

Table 136: viTerminate() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to an object.
eventType	IN	Logical event identifier.
handler	IN	Interpreted as a valid reference to a handler to be uninstalled by a client application.
userHandle		A value specified by an application that can be used for identifying handlers uniquely in a session for an event.

Return values

Table 137: viUninstallHandler() completion codes

Completion codes	Description
VI_SUCCESS	Event handler successfully uninstalled.

Table 138: viUninstallHandler() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_INV_EVENT	Specified event type is not supported by the resource.
VI_ERROR_INV_HNDLR_REF	Either the specified handler reference or the user context value (or both) does not match any installed handler.
VI_ERROR_HNDLR_NINSTALLED	A handler is not currently installed for the specified event.

C example

// Cleanup and exit
status = viDisableEvent(vi, VI_EVENT_SERVICE_REQ, VI_HNDLR);
if (status < VI_SUCCESS) goto error;
status = viUninstallHandler(vi, VI_EVENT_SERVICE_REQ,
ServiceReqEventHandler, NULL);
if (status < VI_SUCCESS) goto error;</pre>

viClose(vi); viClose(rm);

Comments

The viUninstallHandler() operation allows applications to uninstall handlers for events on sessions.

- Applications should also specify the value in the userHandle parameter that was passed while installing the handler. VISA identifies handlers uniquely using the handler reference and this value.
- · All the handlers, for which the handler reference and the userhandle value matches, are uninstalled.

Table 139: Special values for handler parameter with viUninstallHandler()

Value	Description
VI_ANY_HNDLR	Causes the operation to uninstall all the handlers with thematching value in the userHandle
	parameter.

See also

Handling Events

vilnstallHandler (vi, eventType, handler, userHandle)

viUnlock (vi)

Usage

Relinquish a lock on the specified resource.

C format

```
ViStatus viUnlock (ViSession vi)
```

Visual basic format

viUnlock (ByVal vi As Long) As Long

Parameters

Table 140: viUnlock() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.

Return values

Table 141: viUninstallHandler() completion codes

Completion codes	Description
VI_SUCCESS	Lock successfully relinquished.
VI_SUCCESS_NESTED_EXCLUSIVE	Call succeeded, but this session still has nested exclusive locks.
VI_SUCCESS_NESTED_SHARED	Call succeeded, but this session still has nested shared locks.

Table 142: viUnlock() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_SESN_NLOCKED	The current session did not have any lock on the resource.

C example

```
ViSession rm. vi:
char string[256];
ViUInt32 retCnt;
int i = 0;
if (viOpenDefaultRM(&rm) < VI SUCCESS) return;
if (viOpen(rm, "GPIB8::1::INSTR", NULL, NULL, &vi) < VI_SUCCESS)
return;
for (i = 1; i < 100; i++)
viLock(vi, VI_EXCLUSIVE_LOCK, VI_TMO_INFINITE, NULL,
NULL);
if (viWrite(vi, (ViBuf) "ch1:scale?", 10, &retCnt)
< VI SUCCESS) return;
if (viRead(vi, (ViBuf) string, 256, &retCnt)
< VI SUCCESS) return;
printf("%d: scale %s", i, string);
viUnlock(vi);
}
```

Comments

This operation is used to relinquish the lock previously obtained using the viLock() operation.

See also

Locking and Unlocking Resources viLock (vi, lockType, timeout, requestedKey, accessKey)

viUsbControlIn (vi, bmRequestType, bRequest, wValue, wIndex, wLength, buffer, retCount)

Usage

Request arbitrary data from a USB device on the default control port.

C format

```
ViStatus viUsbControlIn (ViSession vi, ViInt16 bmRequestType, ViInt16 bRequest,
ViUInt16 wValue, ViUInt16 wIndex, ViUInt16 wLength, Unsigned char [] buffer,
ViUInt16 retCount);
```

Visual basic format

viUsbControlIn (ByVal vi As Long, ByVal bmRequestType As Integer, ByVal bRequest As Integer, ByVal wValue As Integer, ByVal wIndex As Integer, ByVal wLength As Integer, buffer As Byte, retCount As Integer) As Long

Parameters

Table 143: viUsbContrlln() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
bmRequest-Type	IN	The bmRequestType parameter of the setup stage of a USB control transfer. Refer to the USB specification for further details.
bRequest	IN	The bRequest parameter of the setup stage of a USB control transfer.
wValue	IN	The wValue parameter of the setup stage of a USB control transfer.
wIndex	IN	The windex parameter of the setup stage of a USB control transfer. This is usually the index of the interface or endpoint.
wLength	IN	The wLength parameter of the setup stage of a USB control transfer. This value also specifies the size of the data buffer to receive the data from the optional data stage of the control transfer.
buffer	OUT	The data buffer that receives the data from the optional data stage of the control transfer. This is ignored if wLength is 0.
retCount	OUT	Number of bytes actually transferred in the optional data stage of the control transfer. This parameter may be VI_NULL if you do not need this information.

Return values

Table 144: viUsbContrlln() completion codes

Completion codes	Description
VI_SUCCESS	Operation completed successfully.

Table 145: viUsbContrlln() error codes

Error codes	Description
VI_ERROR_INV_OBJECT	The given session reference is invalid.
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_TMO	Timeout expired before the operation completed.
VI_ERROR_INV_SETUP	Unable to start the write operation because the setup is invalid (due to attributes being set to an inconsistent state).
VI_ERROR_IO	An unknown I/O error occurred during transfer.
VI_ERROR_CONN_LOST	The I/O connection for the given session has been lost.
VI_ERROR_INV_PARAMETER	The value of some parameter, which parameter is unknown, is invalid.
VI_ERROR_INV_MASK	The bmRequestType parameter contains an invalid mask.

C example

```
/#include "stdafx.h"
#include <stdio.h>
#include <memory.h>
#include <visa.h>
#define GET CAPABILITIES 0x07
#define USB DIR IN 0x80
#define USB TYPE CLASS 0x01 << 5
#define USB RECIP INTERFACE 0x01
#define GET CAPABILITIES RESPONSE SIZE 0x18
int tmain(int argc, TCHAR* argv[])
ł
ViSession rm = VI NULL, vi = VI NULL;
ViStatus status;
ViChar buffer[256];
ViInt16 bmRequestType = USB_DIR_IN | USB_TYPE_CLASS |
USB RECIP INTERFACE;
ViInt16 bRequest = GET CAPABILITIES;
ViUInt16 wValue = 0x00;
ViUInt16 wIndex = 0x00;
ViUInt16 wLength = GET CAPABILITIES
RESPONSE SIZE;
ViUInt16 RetCount = 0;
bool bTalk = false;
bool bListen = false;
// Open a default Session
status = viOpenDefaultRM(&rm);
if (status < VI SUCCESS) goto error;
// Open a VISA session to the USB device
status = viOpen(rm, "USB0::1689::1025::Q10033::0::INSTR", VI NULL,
VI NULL, &vi);
//Note: "USB0::1689::1025::Q10033::0::INSTR" is a VISA descriptor for
specific USBTMC instrument.
// Please change this to a valid VISA descriptor name for your USBTMC
instrument.
if (status < VI SUCCESS) goto error;
status = viUsbControlIn (vi, bmRequestType, bRequest, wValue, wIndex,
wLength, (ViPBuf) buffer, &RetCount);
if (status < VI SUCCESS) goto error;
if((buffer[4] \& 0x02) == 1)
{
printf("The Device is Talk Only.\n");
bTalk = true;
if((buffer[4] \& 0x01) == 1)
printf("The Device is Listen Only.\n");
bListen = true;
if((bTalk == false) && (bListen == false))
printf("The Device is capable of both talk & listen.\n");
```

} // Clean up viClose(vi); // Not needed, but makes things a bit more understandable viClose(rm); return 0; error: // Report error and clean up viStatusDesc(vi, status, buffer); fprintf(stderr, "failure: %s\n", buffer if (rm != VI NULL) { viClose(rm); ł return 0:

Comments

This operation can be used to request arbitrary data from a USB device on the default control port.

See also

viUsbControlOut (vi, bmRequestType, bRequest, wValue,wIndex, wLength, buffer)

viUsbControlOut (vi, bmRequestType, bRequest, wValue, wIndex, wLength, buffer)

Usage

Send arbitrary data to a USB device on the default control port.

C format

ViUInt16 viUsbControlOut (ViSession vi, ViInt16 bmRequestType, ViInt16 bRequest, ViUInt16 wValue, ViUInt16 wIndex, ViUInt16 wLength, ViConstBuf buffer);

Visual basic format

viUsbControlOut (ByVal vi As Long, ByVal bmRequestType As Integer, ByVal bRequest As Integer, ByVal wValue As Integer, ByVal wIndex As Integer, ByVal wLength As Integer, buffer As Byte) As Long

Parameters

Table 146: viUsbContrlln() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
bmRequest-Type	IN	The bmRequestType parameter of the setup stage of a USB control transfer. Refer to the USB specification for further details.
bRequest	IN	The bRequest parameter of the setup stage of a USB control transfer.
wValue	IN	The wValue parameter of the setup stage of a USB control transfer.
Table continued		

Table continued...

Name	Direction	Description
wIndex	IN	The windex parameter of the setup stage of a USB control transfer. This is usually the index of the interface or endpoint.
wLength	IN	The wLength parameter of the setup stage of a USB control transfer. This value also specifies the size of the data buffer to receive the data from the optional data stage of the control transfer.
buffer	IN	The data buffer that receives the data from the optional data stage of the control transfer. This is ignored if wLength is 0.

Return values

Table 147: viUsbContrlOut() completion codes

Completion codes	Description
VI_SUCCESS	Operation completed successfully.

Table 148: viUsbContrlOut() error codes

Error codes	Description
VI_ERROR_INV_OBJECT	The given session reference is invalid.
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_TMO	Timeout expired before the operation completed.
VI_ERROR_INV_SETUP	Unable to start the write operation because the setup is invalid (due to attributes being set to an inconsistent state).
VI_ERROR_IO	An unknown I/O error occurred during transfer.
VI_ERROR_CONN_LOST	The I/O connection for the given session has been lost.
VI_ERROR_INV_PARAMETER	The value of some parameter, which parameter is unknown, is invalid.
VI_ERROR_INV_MASK	The bmRequestType parameter contains an invalid mask.

C example

/ UsbControlOut.cpp : Defines the entry point for the console application. // #include "stdafx.h" #include <stdio.h> #include <memory.h> #include <visa.h> #define USB_DIR_OUT 0x00 #define USB_TYPE_STANDARD 0x00 << 5 #define USB_RECIP_ENDPOINT 0x02 #define USB_REQ_CLEAR_FEATURE 0x01 int _tmain(int argc, _TCHAR* argv[]) ł ViSession rm = VI_NULL, vi = VI_NULL; ViStatus status; ViChar buffer[256]; ViUInt32 retCnt = 0;

```
ViInt16 bmRequestType = USB DIR OUT | USB TYPE STANDARD
USB RECIP ENDPOINT;
ViInt16 bRequest = USB_REQ_CLEAR_FEATURE;
ViUInt16 wValue = 0x00;
ViUInt16 wIndex = 0x06;
ViUInt16 wLength = 0x00;
// Open a default Session
status = viOpenDefaultRM(&rm);
if (status < VI SUCCESS) goto error;
// Open a VISA session to the USB device
status = viOpen(rm, "USB0::1689::1025::Q10033::0::INSTR", VI NULL,
VI NULL, &vi);
//Note: "USB0::1689::1025::Q10033::0::INSTR" is a VISA descriptor for
specific USBTMC instrument.
// Please change this to a valid VISA descriptor name for your USBTMC
instrument.
if (status < VI SUCCESS) goto error;
// Sending CLEAR FEATURE
status = viUsbControlOut (vi, bmRequestType, USB REQ CLEAR FEATURE,
wValue, wIndex, wLength, NULL);
if (status < VI SUCCESS) goto error;
// Clean up
viClose(vi); // Not needed, but makes things a bit more understandable
viClose(rm):
return 0;
error:
// Report error and clean up
viStatusDesc(vi, status, buffer);
fprintf(stderr, "failure: %s\n", buffer);
if (rm != VI_NULL) {
viClose(rm);
}
return 0;
}
```

Comments

This operation can be used to send arbitrary data to a USB device on the default control port.

See also

viUsbControlIn (vi, bmRequestType, bRequest, wValue,wIndex, wLength, buffer, retCount)

viVPrintf (vi, writeFmt, params)

Usage

Formats and writes data to a device using a pointer to a variable-length argument list.

C format

ViStatus viVPrintf (ViSession vi, ViConstString writeFmt, ViVAList params)

Visual basic format

viVPrintf (ByVal vi As Long, ByVal writeFmt As String, ByVal params As Any) As Long

Parameters

Table 149: viVPrintf() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
writeFmt	IN	The format string to apply to parameters in ViVAList
params		A pointer to a variable argument list containing the variable number of parameters on which the format string is applied. The formatted data is written to the specified device.

Return values

Table 150: viVPrintf() completion codes

Completion codes	Description
VI_SUCCESS	Parameters are successfully formatted.

Table 151: viVPrintf() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is not valid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_IO	Could not perform write operation because of I/O error.
VI_ERROR_TMO	Timeout expired before write operation completed.
VI_ERROR_INV_FMT	A format specifier in thewriteFmt string is not valid.
VI_ERROR_NSUP_FMT	A format specifier in the writeFmt string is not supported.
VI_ERROR_ALLOC	The system could not allocate a formatted I/O buffer because of insufficient system resources.

C example

#include <stdio.h>
#include <string.h>
#include <visa.h>
#include <visa.h>
#include <stdarg.h>
// My printf which always prepends the command with a header off
ViStatus MyPrintf(ViSession vi, ViString fmt, ...)
{
ViStatus retval;
ViVAList args;
viBufWrite(vi, (ViBuf) "header off", 10, VI_NULL);
va_start(args, fmt);
retval = viVPrintf(vi, fmt, args);

```
va end(args);
return retval:
int main(int argc, char* argv[])
ViSession rm = VI NULL, vi = VI NULL;
ViStatus status;
char buffer[256];
long const start = 1;
long const stop = 500;
// Open a default Session
status = viOpenDefaultRM(&rm);
if (status < VI SUCCESS) goto error;
// Open the gpib device at primary address 1, gpib board 8
status = viOpen(rm, "GPIB0::1::INSTR", VI NULL, VI NULL,
&vi);
if (status < VI SUCCESS) goto error;
status = MyPrintf(vi, "data:start %d;data:stop %d", start,
stop);
if (status < VI SUCCESS) goto error;
viClose(vi); // Not needed, but makes things a bit more
// understandable
viClose(rm);
return 0:
error:
// Report error and clean up
viStatusDesc(vi, status, buffer);
fprintf(stderr, "failure: %s\n", buffer);
if (rm != VI NULL) {
viClose(rm);
}
return 1;
}
```

Comments

This operation is similar to viPrintf() except that params provides a pointer to a variable argument list rather than the variable argument list itself (with separate arg parameters).

See also

Reading and Writing Formatted Data viVScanf (vi, readFmt, params) viVQueryf(vi, writeFmt, readFmt, params)

viVQueryf (vi, writeFmt, readFmt, params)

Usage

Writes and reads formatted data to and from a device using a pointer to a variable-length argument list.

C format

```
ViStatus viVQueryf (ViSession vi, ViConstString writeFmt, ViConstString readFmt,ViVAList params)
```

Visual basic format

viVQueryf (ByVal vi As Long, ByVal writeFmt As String, ByVal readFmt As String, ByVal params As Any) As Long

Parameters

Table 152: viVQueryf() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
writeFmt	IN	The format string to apply to write parameters in ViVAList
readFmt	IN	The format string to apply to read parameters in ViVAList
params	IN OUT	A pointer to a variable argument list containing the variable number of write and read parameters. The write parameters are formatted and written to the specified device. The read parameters store the data read from the device after the format string is applied to the data.

Return values

Table 153: viVQueryf() completion codes

Completion codes	Description
VI_SUCCESS	Successfully completed the Query operation.

Table 154: viVQueryf() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is not valid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_IO	Could not perform write operation because of I/O error.
VI_ERROR_TMO	Timeout expired before read/write operation completed.
VI_ERROR_INV_FMT	A format specifier in the writeFmt or readFmt string is not valid.
VI_ERROR_NSUP_FMT	A format specifier in the writeFmt or readFmt string is not supported.
VI_ERROR_ALLOC	The system could not allocate a formatted I/O buffer because of insufficient system resources.

C example

#include <stdio.h>
#include <visa.h>
#include <stdarg.h>

```
// My own Queryf that flushes the write buffer before doing a query.
ViStatus MyQueryf(ViSession vi, ViConstString writeFmt, ViConstString readFmt, ...)
{
ViStatus retval;
ViVAList args;
// Make sure pending writes are written
retval = viFlush(vi, VI_WRITE_BUF | VI_READ_BUF);
if (retval < VI_SUCCESS) return retval;
// Pass Query on to VISA
va_start(args, readFmt);
retval = viVQueryf(vi, writeFmt, readFmt, args);
va_end(args);
return retval;
}
```

Comments

This operation is similar to viQueryf() except that params provides a pointer to a variable argument list rather than the variable argument list itself (with separate arg parameters).



Note: Because the prototype for this function cannot provide complete type-checking, remember that all output parameters must be passed by reference.

See also

Reading and Writing Formatted Data viVScanf (vi, readFmt, params) viVPrintf(vi, writeFmt, params)

viVScanf (vi, readFmt, params)

Usage

Reads and formats data from a device using a pointer to a variable-length argument list.

C format

```
ViStatus viVScanf (ViSession vi, ViConstString readFmt, ViVAList params)
```

Visual basic format

viVScanf (ByVal vi As Long, ByVal readFmt As String, ByVal params As Any) As Long

Parameters

Table 155: viVScanf() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
readFmt	IN	The format string to apply to read parameters in ViVAList
params		A pointer to a variable argument list containing the variable number of parameters into which the data is read and the format string is applied.

Return values

Table 156: viVScanf() completion codes

Completion Codes	Description
VI_SUCCESS	Data is successfully read and formatted into arg parameters.

Table 157: viVScanf() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is not valid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_IO	Could not perform write operation because of I/O error.
VI_ERROR_TMO	Timeout expired before read operation completed.
VI_ERROR_INV_FMT	A format specifier in thereadFmt string is not valid.
VI_ERROR_NSUP_FMT	A format specifier in the readFmt string is not supported.
VI_ERROR_ALLOC	The system could not allocate a formatted I/O buffer because of insufficient system resources.

C example

```
#include <stdio.h>
#include <visa.h>
#include <stdarg.h>
// My own Scan that flushes the write buffer before doing a query.
ViStatus MyScanf(ViSession vi, ViString readFmt, ...)
{
ViStatus retval;
ViVAList args;
// Make sure pending writes are written
retval = viFlush(vi, VI WRITE BUF);
if (retval < VI SUCCESS) return retval;
// Pass Query on to VISA
va start(args, readFmt);
retval = viVScanf(vi, readFmt, args);
va end(args);
return retval;
}
```

Comments

This operation is similar to viScanf() except that params provides a pointer to a variable argument list rather than the variable argument list itself (with separate arg parameters).



Note: Because the prototype for this function cannot provide complete type-checking, remember that all output parameters must be passed by reference.

See also

Reading and Writing Formatted Data viVQueryf (vi, writeFmt, readFmt, params) viVPrintf(vi, writeFmt, params)

viVSPrintf (vi, buf, writeFmt, params)

Usage

Formats and writes data to a user-specified buffer using a pointer to a variable-length argument list.

C format

```
ViStatus viVSPrintf (ViSession vi, ViPBuf buf, ViConstString writeFmt, ViVAList
params)
```

Visual basic format

viVSPrintf (ByVal vi As Long, ByVal buf As String, ByVal writeFmt As String, ByVal params As Any) As Long

Parameters

Table 158: viVSPrintf() Parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
buf	OUT	Buffer where data is to be written.
writeFmt	IN	The format string to apply to parameters in ViVAList.
params		A pointer to a variable argument list containing the variable number of parameters on which the format string is applied. The formatted data is written to the specified buffer.

Return values

Table 159: viVSPrintf() completion codes

Completion codes	Description
VI_SUCCESS	Parameters are successfully formatted.

Table 160: viVSPrintf() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is not valid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
Table continued	

Table continued...

Error codes	Description
VI_ERROR_INV_FMT	A format specifier in the writeFmt string is not valid.
VI_ERROR_NSUP_FMT	A format specifier in the writeFmt string is not supported.
VI_ERROR_ALLOC	The system could not allocate a formatted I/O buffer because of insufficient system resources.

C example

#include <stdio.h> #include <string.h> #include <visa.h> #include <stdarg.h> // My printf writes directly to the device (no buffering) ViStatus MyPrintf(ViSession vi, ViConstString fmt, ...) ł ViStatus retval; ViVAList args; ViChar buffer[256]; va start(args, fmt); retval = viVSPrintf(vi, (ViBuf) buffer, fmt, args); va_end(args); if (retval >= VI SUCCESS) { retval = viWrite(vi, (ViBuf) buffer, strlen(buffer), VI NULL); } return retval; }

Comments

This operation is similar to viVPrintf() except that the output is not written to the device; it is written to the user-specified buffer. This output buffer is NULL terminated.

If this operation outputs an END indicator before all the arguments are satisfied, the rest of the writeFmt string is ignored and the buffer string is still terminated by a NULL.

See also

Reading and Writing Formatted Data viVSScanf (vi, buf, readFmt, params)

viVSScanf (vi, buf, readFmt, params)

Usage

Reads and formats data from a user specified buffer using a pointer to a variable length argument list.

C format

```
ViStatus viVSScanf (ViSession vi, ViConstBuf buf, ViConstString readFmt, ViVAList params)
```

Visual basic format

viVSScanf (ByVal vi As Long, ByVal buf As String, ByVal readFmt As String, ByVal params As Any) As Long

Parameters

Table 161: viVSScanf() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
buf	IN	Buffer from which data is read and formatted.
readFmt	IN	The format string to apply to parameters in ViVAList.
params		A pointer to a variable argument list with the variable number of parameters into which the data is read and to which the format string is applied.

Return values

Table 162: viVSScanf() completion codes

Completion codes	Description
VI_SUCCESS	Data is successfully read and formatted into arg parametes.

Table 163: viVSScanf() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is not valid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_INV_FMT	A format specifier in the readFmt string is not valid.
VI_ERROR_NSUP_FMT	A format specifier in the readFmt string is not supported.
VI_ERROR_ALLOC	The system could not allocate a formatted I/O buffer because of insufficient system resources.

C example

#include <stdio.h>
#include <string.h>
#include <visa.h>
#include <visa.h>
#include <visdarg.h>
// My scanf reads directly from the device (no buffering).
// The unscanned portions of the buffer will be lost.
ViStatus MyScanf(ViSession vi, ViConstString fmt, ...)
{
ViStatus retval;
ViVAList args;
ViChar buffer[1024];
retval = viRead(vi, (ViBuf) buffer, sizeof(buffer), VI_NULL);

```
if (retval >= VI_SUCCESS)
{
va_start(args, fmt);
retval = viVSScanf(vi, (ViBuf) buffer, fmt, args);
va_end(args);
return retval;
}
```

Comments

The viVSScanf() operation is similar to viVScanf() except that the data is read from a user-specified buffer rather than a device.



Note: Because the prototype for this function cannot provide complete type checking, remember that all output parameters must be passed by reference.

See also

Reading and writing formatted data viVSPrintf (vi, buf, writeFmt, params)

viWaitOnEvent (vi, inEventType, timeout, outEventType, outContext)

Usage

Waits for an occurrence of the specified event for a given session.

C format

```
ViStatus viWaitOnEvent(ViSession vi, ViEventType inEventType, ViUInt32 timeout,ViPEventType outEventType,ViPEvent outContext)
```

Visual basic format

viWaitOnEvent (ByVal viAs Long, ByVal inEventTypeAs Long, ByVal timeoutAs Long, ByVal outEventType As Long, ByVal outcontext As Long) As Long

Parameters

Table 164: viWaitOnEvent() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
inEventType	IN	Logical identifier of the events to wait for.
timeout		Absolute time period in time units that the resource shall wait for a specified event to occur before returning the time elapsed error. The time unit is in milliseconds.
outEventType	OUT	Logical identifier of the event actually received.
outContext	OUT	A handle specifying the unique occurrence of an event.

Return values

Completion codes	Description
VI_SUCCESS	Wait terminated successfully on receipt of an event occurrence. The queue is empty.
VI_SUCCESS_QUEUE_ NEMPTY	Wait terminated successfully on receipt of an event notification. There is still at least one more event occurrence of the type specified by inEventType available for this session.

Table 165: viWaitOnEvent() completion codes

Table 166: viWaitOnEvent() error codes

Error codes	Description
VI_ERROR_INV_SESSION VI_ERROR_INV_OBJECT	The given session or object reference is not valid (both are the same value).
VI_ERROR_INV_EVENT	Specified event type is not supported by the resource.
VI_ERROR_TMO	Specified event did not occur within the specified time period.
VI_ERROR_NENABLED	The session must be enabled for events of the specified type in order to receive them.

C example

viWrite(vi, (ViBuf) "*CLS", 4, VI_NULL);

viWrite(vi, (ViBuf) ":ACQUIRE:STATE 1", 16, VI_NULL);

viwrite(vi, (ViBuf) "*OPC", 4, VI_NULL);

viWaitOnEvent(vi,VI_EVENT_SERVICE_REQ, 5000, &eventType, &context)

viReadSTB(vi, &stb)

Comments

The viWaitOnEvent() operation suspends the execution of a thread of an application and waits for an event of the type specified by inEventTypefor a time period specified by timeout.

- You can only wait for events that have been enabled with the viEnableEvent() operation. Refer to individual event descriptions for context definitions.
- viWaitOnEvent() removes the specified event from the event queue if one that matches the type is available. The process of dequeuing makes an additional space available in the queue for events of the same type.
- When the outContext handle returned from a successful invocation of viWaitOnEvent() is no longer needed, it should be passed to viClose().
- If a session's event queue becomes full and a new event arrives, the new event is discarded.
- The default value of VI_ATTR_MAX_QUEUE_LENGTH is 50.

Table 167: Special values for inEventType parameter with viWaitOnEvents()

Value	Description
VI_ALL_ENABLED_EVENTS	The operation waits for any event that is enabled for the given session.

Table 168: Special values for timeout Parameter with viWaitOnEvents()

Value	Description	
VI_TMO_INFINITE	The operation is suspended indefinitely.	
VI_TMO_IMMEDIATE	The operation is not suspended; therefore, this value can be used to dequeue the events from an event queue.	

The outEventTypeand outContext parameters are optional and can be VI_NULL.

Table 169: Special values for outEventType parameter with viWaitOnEvents()

Value	Description
VI_NULL	Used if the event type is known from the inEventType parameter.

Table 170: Special values for outContext parameter with viWaitOnEvents()

Value	Description	
_	Used if the outContext handle is not needed to retrieve additional information. If that case, VISA will automatically close the event context.	

See also

Handling Events

viDiscardEvents(vi,event, mechanism)

viWrite(vi, buf, count, retCount)

Usage

Writes data synchronously to a device from the specified buffer.

C format

ViStatus viWrite (ViSession vi, ViConstBuf buf, ViUInt32 count, ViPUInt32 retCount)

Visual basic format

```
viWrite (ByVal vi As Long, ByVal buf As String, ByVal count As Long, ByVal retCount As Long) As Long
```

Parameters

Table 171: viWrite() parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
buf	IN	Represents the location of a data block to be sent to device.
count	IN	Number of bytes to be written.

Table continued...

Name	Direction	Description
retCount		Represents the location of an integer that will be set to the number of bytes actually transferred.

Return values

Table 172: viWrite() completion codes

Completion codes	Description
VI_SUCCESS	Transfer completed.

Table 173: viWrite() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is not valid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_NSUP_OPER	The given vi does not support this operation.
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_TMO	Timeout expired before operation completed.
VI_ERROR_RAW_WR_PROT_VIOL	Violation of the raw write protocol occurred during transfer.
VI_ERROR_RAW_RD_PROT_VIOL	Violation of the raw read protocol occurred during transfer.
VI_ERROR_INP_PROT_VIOL	Device reported an input protocol error during transfer.
VI_ERROR_BERR	Bus error occurred during transfer.
VI_ERROR_INV_SETUP	Unable to start write operation because setup is not valid (due to attributes being set to an inconsistent state).
VI_ERROR_NCIC	The interface associated with the given vi is not currently the controller in charge.
VI_ERROR_NLISTENERS	No Listeners condition is detected (both NRFD and NDAC are deasserted).
VI_ERROR_IO	An unknown I/O error occurred during transfer.

C example

if (viWrite(vi, (ViBuf) "*idn?", 5, VI_NULL) < VI_SUCCESS) return; if (viRead(vi, (ViBuf) buffer, sizeof(buffer)--1, &retCnt) < VI_SUCCESS) return; buffer[retCnt] = '\0'; // ensure the string is null terminated printf("id: %s\n", buffer);

Comments

The viWrite() operation synchronously transfers data. The data to be written is in the buffer represented by buf.

- \u0002 This operation returns only when the transfer terminates.
- \u0002 Only one synchronous write operation can occur at any one time.

Value	Description
_	Do not return the number of bytes transferred. This may be useful if it is only important to know whether the operation succeeded or failed.

Table 174: Special value for retCount parameter with viWrite()

See also

```
Reading and writing formatted data viRead (vi, buf, count, retCount)
```

viWriteAsync (vi, buf, count, jobld)

Usage

Writes data asynchronously to a device from the specified buffer.

C format

```
ViStatus viWriteAsync (ViSession vi, ViConstBuf buf, ViUInt32 count, ViPJobId retCount)
```

Visual basic format

Not Applicable

Parameters

Table 175: viWriteAsync() parameters

Name	Direction	Description
vi	IN	Uniquelogical identifier to a session.
buf	IN	Represents the location of a data block to be sent to device.
count	IN	Number of bytes to be written.
jobld		Represents the location of a variable that will be set to the job identifier of this asynchronous write operation.

Return values

Table 176: viWriteAsync() completion codes

Completion codes	Description
VI_SUCCESS	Asynchronous write operation successfully queued.
VI_SUCCESS_SYNC	Write operation performed synchronously.

Table 177: viWriteAsync() error codes

Error codes	Description
VI_ERROR_INV_SESSION VI_ERROR_INV_OBJECT	The given session or object reference is invalid (both are the same value).
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_QUEUE_ERROR	Unable to queue write operation.

C example

```
// rwwait.cpp
//
#include <stdio.h>
#include <string.h>
#include <windows.h>
#include "visa.h"
// viReadAsync/viWriteAsync example --
// These commands can potentially decrease test time by allowing
// several read or write commands to happen in parallel.
int main(int argc, char* argv[])
ViSession rm, vi[2];
ViJobId jobid[2];
ViStatus status;
char string[2][256];
ViEventType eventType[2];
ViEvent event[2];
int i;
// clear strings
for (i = 0; i < 2; i++)
memset(string[i], 0, 256);
}
// Open the default RM
status = viOpenDefaultRM(&rm);
if (status < VI SUCCESS) goto error;
// Open multiple devices
status = viOpen(rm, "GPIB0::1::INSTR", NULL, NULL, &vi[0]);
if (status < VI_SUCCESS) goto error;
status = viOpen(rm, "GPIB8::1::INSTR", NULL, NULL, &vi[1]);
if (status < VI SUCCESS) goto error;
// Enable waiting on the events
for (i = 0; i < 2; i++)
status = viEnableEvent(vi[i], VI_EVENT_IO_COMPLETION,
VI_QUEUE, VI_NULL);
if (status < VI_SUCCESS) goto error;
}
// Write commands to several devices (this allows
// several writes to be done in parallel)
for (i = 0; i < 2; i++) {
status = viWriteAsync(vi[i], (ViBuf) "*idn?",
5, &jobid[i]);
```

```
if (status < VI SUCCESS) goto error;
}
// Wait for completion on all of the devices
for (i = 0; i < 2; i++)
viWaitOnEvent(vi[i], VI EVENT IO COMPLETION,
INFINITE, &eventType[i], &event[i]);
}
// Queue the read for all the devices (this allows
// several reads to be done im parallel)
for (i = 0; i < 2; i++) {
status = viReadAsync(vi[i], (ViBuf) string[i], 256,
&jobid[i]);
if (status < VI SUCCESS) goto error;
ł
// Wait for all the reads to complete
for (i = 0; i < 2; i++) {
viWaitOnEvent(vi[i], VI EVENT IO COMPLETION,
INFINITE, &eventType[i], &event[i]);
}
// Write out the *idn? strings.
for (i = 0; i < 2; i++) {
printf("%d: %s\n", i, string[i]);
}
// Cleanup and exit
for (i = 0; i < 2; i++)
status = viDisableEvent(vi[i], VI EVENT IO COMPLETION,
VI QUEUE);
if (status < VI SUCCESS) goto error;
}
viClose(rm);
return 0;
error:
viStatusDesc(rm, status, string[0]);
fprintf(stderr, "Error: %s\n", (ViBuf) string[0]);
return 0;
}
```

Comments

The viWriteAsync() operation asynchronously transfers data. The data to be written is in the buffer represented by buf.

- This operation normally returns before the transfer terminates.
- Before calling this operation, you should enable the session for receiving I/O completion events. After the transfer has completed, an I/O completion event is posted.
- The operation returns a job identifier that you can use with either viTerminate() to abort the operation or with an I/O completion event to identify which asynchronous write operation completed.
- Since an asynchronous I/O request could complete before the vWriteAsync() operation returns, and the I/O completion event can be distinguished based on the job identifier, an application must be made aware of the job identifier before the first moment that the I/O completion event could possibly occur. Setting the output parameter jobId before the data transfer even begins ensures that an application can always match the jobId parameter with the VI_ATTR_JOB_ID attribute of the I/O completion event.
- If multiple jobs are queued at the same time on the same session, an application can use the jobId to distinguish the jobs, as they are unique within a session.

- The viWriteAsync() operation MAY be implemented synchronously, which could be done by using the viWrite() operation. This means
 that an application can use the asynchronous operations transparently even if a low level driver only supports synchronous data
 transfers. If the viWriteAsync() operation is implemented synchronously and a given invocation of the operation is valid, the operation
 returns VI_SUCCESS_SYNC AND all status information is returned in a VI_EVENT_IO_COMPLETION.
- The status code VI_ERROR_RSRC_LOCKED can be returned either immediately or from the VI_EVENT_IO_COMPLETION event.
- For each successful call to viWriteAsync(), there is one and only one VI_EVENT_IO_COMPLETION event occurrence.

Table 178: Special value for jobId parameter with viWriteAsync()

Value	Description	
VI_NULL	Do not return a job identifier. This option may be useful if only one asynchronous operation	
	will be pending at a given time.	

See also

Asychronous Read/Write viReadAsync(vi,buf, count, jobld) ViTerminate (vi, degree, jobld)

viWriteFromFile (vi, fileName, count, retCount)

Usage

Take data from a file and write it to a device synchronously.

C format

```
ViStatus viWriteFromFile(ViSession vi, ViString fileName, ViUInt32 count, ViUInt32 retCount)
```

Visual basic format

```
viWriteFromFile(By Val vi As Long, By Val fileName As String, By Val count As Long, By Val retCount As Long) As Long
```

Parameters

Table 179: viWriteFromFile parameters

Name	Direction	Description
vi	IN	Unique logical identifier to a session.
fileName	IN	Name of the file from which data will be read.
count	IN	Number of bytes to be written.
retCount	OUT	Number of bytes actually transferred.

Return values

Table 180: viWriteFromFile completion codes

Completion codes	Description
VI_SUCCESS	Transfer completed.

Table 181: viWriteFromFile() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is not valid (both are the same value).
VI_ERROR_INV_OBJECT	
VI_ERROR_NSUP_OPER	The given vi does not support this operation.
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by vi has been locked for this kind of access.
VI_ERROR_TMO	Timeout expired before operation completed.
VI_ERROR_RAW_WR_PROT_VIOL	Violation of the raw write protocol occurred during transfer.
VI_ERROR_RAW_RD_PROT_VIOL	Violation of the raw read protocol occurred during transfer.

Table 182: viWriteFromFile() error codes (cont.)

Error codes	Description
VI_ERROR_INP_PROT_VIOL	Device reported an input protocol error during transfer.
VI_ERROR_BERR	Bus error occurred during transfer.
VI_ERROR_NCIC	The interface associated with the given vi is not currently the controller in charge.
VI_ERROR_NLISTENERS	No Listeners condition is detected (both NRFD and NDAC are deasserted).
VI_ERROR_IO	An unknown I/O error occurred during transfer.
VI_ERROR_FILE_ACCESS	An error occurred while trying to open the specified file. Possible reasons include a not valid path or lack of access rights.
VI_ERROR_FILE_IO	An error occurred while accessing the specified file.
VI_ERROR_CONN_LOST	The I/O connection for the given session has been lost.

C example

ViSession rm, vi; ViStatus status = VI_SUCCESS; ViUInt32 retCount; if (viOpenDefaultRM(&rm) < VI_SUCCESS) return; if (viOpen(rm, "GPIB8::1::INSTR", NULL, NULL, &vi) < VI_SUCCESS) return; status = viWriteFromFile(vi,"curve.bin",20,&retCount); viClose(vi); viClose(rm);

This write operation synchronously transfers data. The file specified in fileName is opened in binary read-only mode, and the data (up to the end-of-file, or the number of bytes specified in count) is read. The data is then written to the device. This operation returns only when the transfer terminates.

This operation is useful for sending data that was already processed or formatted.

See also

Reading and writing formatted data viWrite (vi, buf, count, retCount) viReadToFile (vi, fileName, count, retCount)

viPxiReserveTriggers(vi, cnt, trigBuses, trigLines, failureIndex)

Usage

Reserves multiple trigger lines that the caller can then map and/or assert.

Parameters

Table 183: viPxiReserveTriggers() parameters

Name	Direction	Туре	Description
vi	IN	ViSession	Unique logical identifer to a session.
cnt	IN	Vilnt16	Number of trigger bus/line pairs to follow.
trigBuses	IN	ViAInt16	Array of trigger buses. The size of this array is specified in cnt.
trigLines	IN	ViAInt16	Array of trigger lines. The size of this array is specified in cnt.
failure Index	OUT	Vilnt16	Specifies the 0-based index of the firsr trigger bus/line pair that could not be reserved, if this function returns error code directly related to reserving triggers. On success, this output parameter contains the value -1. For any other status code returned, the value of this output parameter is undefined and should not be used.

Return values

Type vistatus: This is the operational return status. It return either a completion code or an error code as follows.

Table 184: viPxiReserveTriggers() completion codes

Completion code	Description
VI_SUCCESS	Operation completed successfully.

Table 185: viPxiReserveTriggers() error codes

Error codes	Description
VI_ERROR_INV_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_OBJECT	
Table continued	

[lable continued...

Error codes	Description
VI_ERROR_NSUP_OPER	The given vi does not support this operation.
VI_ERROR_RSRC_LOCKED	Specified operation could not be performed because the resource identified by $v \pm$ has been locked by this kind of access.
VI_ERROR_INV_LENGTH	Invalid count specified.
VI_ERROR_IO	Could not perform operation because of I/O error.
VI_ERROR_LINE_IN_USE	One of the specified lines is currently in use.
VI_ERROR_INV_LINE	One of the specified lines is invalid.
VI_ERROR_NSUP_LINE	One of the specified lines is not supported by this VISA implementation.

Attributes summary

The table summarizes TekVISA attributes by category. Within categories, attributes appear in alphabetical order.

Table 186: Table of VISA attributes by category

Attribute	Description
Resource attributes	
VI_ATTR_MAX_QUEUE_LENGTH	Specifies themaximumnumber of events that can be queued at any time on the given session.
VI_ATTR_RM_SESSION	Specifies the session of the Resource Manager that was used to open this session.
VI_ATTR_RSRC_IMPL_VERSION	Resource version that uniquely identifies each of the different revisions or implementations o a resource.
VI_ATTR_RSRC_LOCK_STATE	The current locking state of the resource on the given session.
VI_ATTR_RSRC_MANF_ID	A value that corresponds to the VXI manufacturer ID of the manufacturer that created the VISA implementation.
VI_ATTR_RSRC_MANF_NAME	A string that corresponds to the VXImanufacturer name of the manufacturer that created the VISA implementation.
VI_ATTR_RSRC_NAME	The unique identifier for a resource.
VI_ATTR_RSRC_SPEC_VERSION	Resource version that uniquely identifies the version of the VISA specification to which the implementation is compliant.
VI_ATTR_USER_DATA	Data used privately by the application for a particular session.
Interface attributes	
VI_ATTR_INTF_INST_NAME	Human-readable text describing the given interface.
VI_ATTR_INTF_NUM	Board number for the given interface.
VI_ATTR_INTF_TYPE	Specifies the interface type of the givensession.
VI_ATTR_IO_PROT	Specifies which protocol to use, depending on the type of interface.
Serial device attributes	
VI_ATTR_ASRL_AVAIL_NUM	Shows the number of bytes available in the global receive buffer.
VI_ATTR_ASRL_BAUD	The baud rate of the interface.
VI_ATTR_ASRL_CTS_STATE	Shows the current state of the Clear-to-Send (CTS) input signal.
VI_ATTR_ASRL_DATA_BITS	The number of data bits contained in eachframe (5 to 8).
VI_ATTR_ASRL_DCD_STATE	Shows the current state of the Data Carrier Detect (DCD) input signal.
VI_ATTR_ASRL_DSR_STATE	Shows the current state of the Data Set Ready (DSR) input signal.
VI_ATTR_ASRL_DTR_STATE	Used to manually assert or unassert theData Terminal Ready (DTR) output signal.
VI_ATTR_ASRL_END_IN	Indicates the method used to terminate readoperations.
VI_ATTR_ASRL_END_OUT	Indicates the method used to terminate write operations.
VI_ATTR_ASRL_FLOW_CNTRL	Indicates the type of flow control used by the transfer mechanism.
VI_ATTR_ASRL_PARITY	The parity used with every frame transmittedand received.
VI_ATTR_ASRL_REPLACE_CHAR	Specifies the character to be used to replace incoming characters that arrive with errors

Attribute	Description
VI_ATTR_ASRL_RI_STATE	Shows the current state of the Ring Indicator (RI) input signal.
VI_ATTR_ASRL_RTS_STATE	Used to manually assert or unassert the Request To Send (RTS) output signal.
VI_ATTR_ASRL_STOP_BITS	The number of stop bits used to indicate theend of a frame.
VI_ATTR_ASRL_XOFF_CHAR	Specifies the value of the XOFF character used for XON/XOFF flow control (both directions)
VI_ATTR_ASRL_XON_CHAR	Specifies the value of the XON character used for XON/XOFF flow control (both directions).
GPIB device attributes	
VI_ATTR_GPIB_PRIMARY_ADDR	Primary address of the GPIB device used by the given session.
VI_ATTR_GPIB_READDR_EN	Specifies whether to use repeat addressing before each read or write operation.
VI_ATTR_GPIB_SECONDARY_ADDR	Secondary address of the GPIB device used by the given session.
VI_ATTR_GPIB_UNADDR_EN	Specifies whether to unaddress the device (UNT and UNL) after each read or write operation.
Read/Write attributes	
VI_ATTR_RD_BUF_OPER_MODE	Determines the operational mode of the read buffer.
VI_ATTR_SEND_END_EN	Specifies whether to assert END during the transfer of the last byte of the buffer.
VI_ATTR_SUPPRESS_END_EN	Specifies whether to suppress the END indicator termination.
VI_ATTR_TERMCHAR	Termination character.
VI_ATTR_TERMCHAR_EN	Flag that determines whether the read operation should terminate when a termination character is received.
VI_ATTR_WR_BUF_OPER_MODE	Determines the operational mode of the write buffer.
Event attributes	
VI_ATTR_BUFFER	Contains the address of a buffer that was used in an asynchronous operation.
VI_ATTR_EVENT_TYPE	Unique logical identifier of the event.
VI_ATTR_JOB_ID	Contains the job ID of the asynchronous operation that has completed.
VI_ATTR_OPER_NAME	The name of the operation generating the event.
VI_ATTR_RET_COUNT	Contains the actual number of elements that were asynchronously transferred.
VI_ATTR_STATUS	Contains the return code of the asynchronous I/O operation that has completed or status code returned by an operation generating an error.
Miscellaneous attributes	
VI_ATTR_TMO_VALUE	Minimum timeout value to use, in milliseconds.
VI_ATTR_TRIG_ID	Identifier for the current triggering mechanism.
USBTMC device attributes	
VI_ATTR_USB_INTFC_NUM	Specifies the USB interface number of the device to which the session is connected.
VI_ATTR_USB_MAX_INTR_SIZE	Specifies the maximum number of bytes that the USB device will send on the interrupt-IN pipe.
VI_ATTR_USB_PROTOCOL	Specifies the USB protocol number.
VI_ATTR_USB_RECV_INTR_DATA	Specifies the actual data that was received from the USB interrupt-IN pipe.
VI_ATTR_USB_RECV_INTR_SIZE	Specifies the size of the data that was received from the USB interrupt-IN pipe.
VI_ATTR_USB_SERIAL_NUM	Shows the serial number of the USB instrument. Used only for display purposes.

Attribute	Description	
TCPIP specific INSTR/SOCKET resource attributes		
VI_ATTR_TCPIP_ADDR	Specifies the TCPIP address of the device to which the session is connected.	
VI_ATTR_TCPIP_HOSTNAME	Specifies the host name of the device.	
VI_ATTR_TCPIP_KEEPALIVE	An application can request a TCP/IP provider to enable the use of keep-alive packets on TCP connections.	
VI_ATTR_TCPIP_NODELAY	Disables the Nagle algorithm when the attribute is enabled.	
VI_ATTR_TCPIP_PORT	Specifies the port number for a given TCPIP address.	

Attributes

The following TekVISA attributes are presented in alphabetical order.

VI_ATTR_ASRL_AVAIL_NUM

Usage

Shows the number of bytes available in the global receive buffer.

Table 187: VI_ATTR_ASRL_AVAIL_NUM Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt32	0 to FFFFFFFh	0	Read Only Global

Comments

Applicable to serial devices.

See also

Controlling the Serial I/O Buffers Setting and Retrieving Attributes

VI_ATTR_ASRL_BAUD

Usage

The baud rate of the interface.

Table 188: VI_ATTR_ASRL_BAUD Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt32	0 to FFFFFFFh	9600	Read/Write Global

Comments

Applicable to serial devices. Although represented as an unsigned 32-bit integer so that any baud rate can be used, it usually requires a commonly used rate such as 300, 1200, 2400, or 9600 baud.

See also

Setting and Retrieving Attributes

VI_ATTR_ASRL_CTS_STATE

Usage

Shows the current state of the Clear-to-Send (CTS) input signal.

Table 189: VI_ATTR_ASRL_CTS_STATE Attribute

Data Type	Range of Values	Default	Access Privilege
Vilnt16	VI_STATE_ASSERTED	N/A	Read Only Global
	VI_STATE_UNASSERTED		
	VI_STATE_UNKNOWN		

Comments

Applicable to serial devices.

See also

Setting and Retrieving Attributes VI_ATTR_ASRL_FLOW_CNTRL VI_ATTR_ASRL_RTS_STATE

VI_ATTR_ASRL_DATA_BITS

Usage

The number of data bits contained in each frame (5 to 8).

Table 190: VI_ATTR_ASRL_DATA_BITS Attribute

Data Type	Range of Values	Default	Access Privilege
ViUint16	5 to 8	8	Read/Write Global

Comments

Applicable to serial devices. The data bits for each frame are located in the low-order bits of every byte stored in memory.

See also

Setting and Retrieving Attributes

VI_ATTR_ASRL_DCD_STATE

Usage

Shows the current state of the Data Carrier Detect (DCD) input signal.

Table 191: VI_ATTR_ASRL_DCD_STATE Attribute

Data Type	Range of Values	Default	Access Privilege
Vilnt16	VI_STATE_ASSERTED	N/A	Read Only Global
	VI_STATE_UNASSERTED		
	VI_STATE_UNKNOWN		

Applicable to serial devices. The DCD signal is often used by modems to indicate the detection of a carrier (remote modem) on the telephone line. The DCD signal is also known as Receive Line Signal Detect (RLSD).

See also

Setting and Retrieving Attributes

VI_ATTR_ASRL_DSR_STATE

Usage

Shows the current state of the Data Set Ready (DSR) input signal.

Table 192: VI_ATTR_ASRL_DSR_STATE Attribute

Data Type	Range of Values	Default	Access Privilege
Vilnt16	VI_STATE_ASSERTED	N/A	Read Only Global
	VI_STATE_UNASSERTED		
	VI_STATE_UNKNOWN		

Comments

Applicable to serial devices.

See also

Setting and Retrieving Attributes VI_ATTR_ASRL_FLOW_CNTRL VI_ATTR_ASRL_DTR_STATE

VI_ATTR_ASRL_DTR_STATE

Usage

Used to manually assert or unassert the Data Terminal Ready (DTR) output signal.

Table 193: VI_ATTR_ASRL_DTR_STATE Attribute

Data Type	Range of Values	Default	Access Privilege
Vilnt16	VI_STATE_ASSERTED	N/A	Read/Write Global
	VI_STATE_UNASSERTED		
	VI_STATE_UNKNOWN		

Comments

Applicable to serial devices.

See also

Setting and Retrieving Attributes VI_ATTR_ASRL_FLOW_CNTRL VI_ATTR_ASRL_DSR_STATE

VI_ATTR_ASRL_END_IN

Usage

Indicates the method used to terminate read operations.

Table 194: VI_ATTR_ASRL_END_IN Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt16	VI_ASRL_END_NONE	VI_ASRL_END_TERMCHAR	Read/Write Local
	VI_ASRL_END_LAST_BIT		
	VI_ASRL_END_TERMCHAR		

Comments

Applicable to serial devices.

- If set to VI_ASRL_END_NONE, the read will not terminate until all of the requested data is received (or an error occurs).
- If set to VI_ASRL_END_LAST_BIT, the read will terminate as soon as a character arrives with its last bit set. For example, if VI_ATTR_ASRL_DATA_BITS is set to 8, the read will terminate when acharacter arrives with the 8th bit set.
- If set to VI_ASRL_END_TERMCHAR, the read will terminate as soon as the character in VI_ATTR_TERMCHAR is received.

See also

Setting and Retrieving Attributes

VI_ATTR_TERMCHAR

VI_ATTR_ASRL_END_OUT

Usage

Indicates the method used to terminate write operations.

Table 195: VI_ATTR_ASRL_END_OUT Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt16	VI_ASRL_END_NONE	VI_ASRL_END_NONE	Read/Write Local
	VI_ASRL_END_LAST_BIT		
	VI_ASRL_END_TERMCHAR		
	VI_ASRL_END_BREAK		

Applicable to serial devices.

- If set to VI_ASRL_END_NONE, the write will not append anything to the data being written.
- If set to VI_ASRL_END_BREAK, the write will transmit a break after all the characters for the write have been sent.
- If set to VI_ASRL_END_LAST_BIT, the write will send all but the last character with the last bit clear, then transmit the last character
 with the last bit set. For example, if VI_ATTR_ASRL_DATA_BITS is set to 8, the write will clear the 8th bit for all but the last character,
 then transmit the last character with the 8th bit set.
- If set to VI_ASRL_END_TERMCHAR, the write will send the character in VI_ATTR_TERMCHAR after the data being transmitted.

See also

Setting and Retrieving Attributes

VI_ATTR_TERMCHAR

VI_ATTR_ASRL_FLOW_CNTRL

Usage

Indicates the type of flow control used by the transfer mechanism.

Table 196: VI_ATTR_ASRL_FLOW_CNTRL Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt16	VI_ASRL_FLOW_NONE	VI_ASRL_FLOW_NONE	Read/Write Global
	VI_ASRL_FLOW_XON_XOFF		
	VI_ASRL_FLOW_RTS_CTS		
	VI_ASRL_FLOW_DTR_DSR		

Comments

Applicable to serial devices.

- If set to VI_ASRL_FLOW_NONE, the transfer mechanism does not use flow control, and buffers on both sides of the connection are
 assumed to be large enough to hold all data transferred.
- If set to VI_ASRL_FLOW_XON_XOFF, the transfer mechanism uses the XON and XOFF characters to perform flow control.
 - It controls input flow by sending XOFF when the receive buffer is nearly full.
 - It controls the output flow by suspending transmission when XOFF is received.
- If set to VI_ASRL_FLOW_RTS_CTS, the transfer mechanism uses the RTSoutput signal and the CTS input signal to perform flow control.
 - It controls input flow by unasserting the RTS signal when the receive buffer is nearly full.
 - · It controls output flow by suspending the transmission when the CTS signal is unasserted.
 - In this case, the VI_ATTR_ASRL_RTS_STATE attribute is ignored when changed, but can be read to determine whether the background flow control is asserting or unasserting the signal.
- If set to VI_ASRL_FLOW_DTR_DSR, the transfer mechanism uses the DTR output signal and the DSR input signal to perform flow control.

- It controls input flow by unasserting the DTR signal when the receive buffer is nearly full, and it controls output flow by suspending the transmission when the DSR signal is unasserted.
- This attribute can specify multiple flow control mechanisms by bit-ORing multiple values together. However, certain combinations may not be supported by all serial ports and/or operating systems.

See also

Setting and Retrieving Attributes

VI_ATTR_ASRL_PARITY

Usage

The parity used with every frame transmitted and received.

Table 197: VI_ATTR_ASRL_PARITY Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt16	VI_ASRL_PAR_NONE	VI_ASRL_PAR_NONE	Read/Write Local
	VI_ASRL_PAR_ODD		
	VI_ASRL_PAR_EVEN		
	VI_ASRL_PAR_MARK		
	VI_ASRL_PAR_SPACE		

Comments

Applicable to serial devices.

- VI_ASRL_PAR_MARK means that the parity bit exists and is always 1.
- VI_ASRL_PAR_SPACE means that the parity bit exists and is always 0.

See also

Setting and Retrieving Attributes

VI_ATTR_ASRL_REPLACE_CHAR

Usage

Specifies the character to be used to replace incoming characters that arrive with errors (such as parity error).

Table 198: VI_ATTR_ASRL_REPLACE_CHAR Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt8	0 to FFh	0	Read/Write Local

Comments

Applicable to serial devices.

See also

Setting and Retrieving Attributes

VI_ATTR_ASRL_RI_STATE

Usage

Shows the current state of the Ring Indicator (RI) input signal.

Table 199: VI_ATTR_ASRL_RI_STATE Attribute

Data Type	Range of Values	Default	Access Privilege
Vilnt16	VI_STATE_ASSERTED	N/A	Read Only Global
	VI_STATE_UNASSERTED		
	VI_STATE_UNKNOWN		

Comments

Applicable to serial devices. The RI signal is often used by modems to indicate that the telephone line is ringing.

See also

Setting and Retrieving Attributes

VI_ATTR_ASRL_RTS_STATE

Usage

Used to manually assert or unassert the Request To Send (RTS) output signal.

Table 200:

Data Type	Range of Values	Default	Access Privilege
Vilnt16	VI_STATE_ASSERTED	N/A	Read/Write Global
	VI_STATE_UNASSERTED		
	VI_STATE_UNKNOWN		

Comments

Applicable to serial devices.

When the VI_ATTR_ASRL_FLOW_CNTRL attribute is set to VI_ASRL_FLOW_RTS_CTS, this attribute is ignored when changed, but can be read to determine whether the background flow control is asserting or unasserting the signal.

See also

Setting and Retrieving Attributes VI_ATTR_ASRL_FLOW_CNTRL

VI_ATTR_ASRL_CTS_STATE

VI_ATTR_ASRL_STOP_BITS

Usage

The number of stop bits used to indicate the end of a frame.

Table 201: VI_ATTR_ASRL_STOP_BITS Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt16	VI_ASRL_STOP_ONE	VI_ASRL_STOP_ONE	Read/Write Global
	VI_ASRL_STOP_ONE5		
	VI_ASRL_STOP_TWO		

Comments

Applicable to serial devices. The value VI_ASRL_STOP_ONE5 indicates one--and--one--half (1.5) stop bits.

See also

Setting and Retrieving Attributes

VI_ATTR_ASRL_XOFF_CHAR

Usage

Specifies the value of the XOFF character used for XON/XOFF flow control (both directions).

Table 202: VI_ATTR_ASRL_XOFF_CHAR Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt8	0 to FFh	<ctrl-s> (13h)</ctrl-s>	Read/Write Local

Comments

Applicable to serial devices. If XON/XOFF flow control (software handshaking) is not being used, the value of this attribute is ignored.

See also

Setting and Retrieving Attributes VI_ATTR_ASRL_FLOW_CNTRL VI_ATTR_ASRL_XON_CHAR

VI_ATTR_ASRL_XON_CHAR

Usage

Specifies the value of the XON character used for XON/XOFF flow control (both directions).

Table 203: VI_ATTR_ ASRL_XON_CHAR Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt8	0 to FFh	<ctrl-q> (11h)</ctrl-q>	Read/Write Local

Comments

Applicable to serial devices. If XON/XOFF flow control (software handshaking) is not being used, the value of this attribute is ignored.

See also

Setting and Retrieving Attributes VI_ATTR_ASRL_FLOW_CNTRL VI_ATTR_ASRL_XOFF_CHAR

VI_ATTR_BUFFER

Usage

Contains the address of a buffer that was used in an asynchronous operation.

Table 204: VI_ATTR_BUFFER Attribute

Data Type	Range of Values	Default	Access Privilege
ViBuf	N/A	N/A	Read Only

Comments

This attribute is used to check the buffer after event I/O completion.

See also

Setting and Retrieving Attributes Events VI_EVENT_IO_COMPLETION

VI_ATTR_EVENT_TYPE

Usage

Unique logical identifier of the event.

Table 205: VI_ATTR_EVENT_TYPE Attribute

Data Type	Range of Values	Default	Access Privilege
ViEventType	0 to FFFFFFFh	N/A	Read Only

Comments

This attribute is used to identify one of the event types listed in the section on Events.

See also

Setting and Retrieving Attributes

Events

VI_ATTR_GPIB_PRIMARY_ADDR

Usage

Primary address of the GPIB device used by the given session.

Table 206: VI_ATTR_GPIB_PRIMARY_ADDR Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt16	0 to 30	N/A	Read Only Global

Comments

Applicable to GPIB devices. See the viOpen() operation for more information about the format for addressing GPIB devices.

See also

Setting and Retrieving Attributes VI_ATTR_RSRC_NAME viOpen()

VI_ATTR_GPIB_READDR_EN

Usage

Specifies whether to use repeat addressing before each read or write operation.

Table 207: VI_ATTR_GPIB_READDR_EN Attribute

Data Type	Range of Values	Default	Access Privilege
Boolean	VI_TRUE	VI_TRUE	Read/Write Local
	VI_FALSE		

Applicable to GPIB devices.

See also

Setting and Retrieving Attributes VI_ATTR_GPIB_UNADDR_EN

VI_ATTR_GPIB_SECONDARY_ADDR

Usage

Secondary address of the GPIB device used by the given session.

Table 208: VI_ATTR_GPIB_SECONDARY_ADDR Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt16	0 to 30	VI_NO_SEC_ADDR	Read Only Global
	VI_NO_SEC_ADDR		

Comments

Applicable to GPIB devices. See the viOpen() operation for more information about the format for addressing GPIB devices.

See also

Setting and Retrieving Attributes VI_ATTR_RSRC_NAME viOpen()

VI_ATTR_GPIB_UNADDR_EN

Usage

Specifies whether to unaddress the device (UNT and UNL) after each read or write operation.

Table 209: VI_ATTR_GPIB_UNADDR_EN Attribute

Data Type	Range of Values	Default	Access Privilege
ViBoolean	VI_TRUE	VI_FALSE	Read/Write Local
	VI_FALSE		

Comments

Applicable to GPIB devices.

See also

Setting and Retrieving Attributes VI_ATTR_GPIB_READDR_EN

VI_ATTR_INTF_INST_NAME

Usage

Specifies whether to unaddress the device (UNT and UNL) after each read or write operation.

Table 210: VI_ATTR_INTF_INST_NAME Attribute

Data Type	Range of Values	Default	Access Privilege
ViString	N/A	N/A	Read Only Global

Comments

Applicable to GPIB and serial interfaces.

See also

Setting and Retrieving Attributes

VI_ATTR_INTF_NUM

VI_ATTR_INTF_NUM

Usage

Board number for the given interface.

Table 211: VI_ATTR_INTF_NUM Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt16	0 to FFFFh	0	Read Only Global

Comments

Applicable to GPIB and serial interfaces.

See also

Setting and Retrieving Attributes VI_ATTR_INTF_INST_NAME

VI_ATTR_INTF_TYPE

Usage

Specifies the interface type of the given session.

Table 212: VI_ATTR_INTF_TYPE Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt16	VI_INTF_GPIB	N/A	Read Only Global
	VI_INTF_ASRL		

Comments

Applicable to GPIB and serial interfaces.

See also

Setting and Retrieving Attributes

VI_ATTR_IO_PROT

Usage

Specifies which protocol to use, depending on the type of interface.

Table 213: VI_ATTR_IO_PROT Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt16	VI_NORMAL	VI_NORMAL	Read/Write Local
	VI_HS488		
	VI_ASRL488		

Comments

Choices depend of interface type:

- With GPIB interfaces, you can choose between normal and high-speed (HS488) data transfers.
- With serial interfaces, you can choose between normal and ASRL488-style transfers, in which case the viAssertTrigger(), viReadSTB(), and viClear() operations send 488.2-defined strings.

See also

Setting and Retrieving Attributes Controlling the Serial I/O Buffers viAssertTrigger() viReadSTB() viClear()

VI_ATTR_JOB_ID

Usage

Contains the job ID of the asynchronous operation that has completed.

Table 214: VI_ATTR_Job_ID Attribute

Data Type	Range of Values	Default	Access Privilege
ViJobID	N/A	N/A	Read Only

Comments

This attribute is used to check the job ID after event I/O completion

See also Setting and Retrieving Attributes Events

VI_EVENT_IO_COMPLETION

VI_ATTR_MAX_QUEUE_LENGTH

Usage

Specifies the maximum number of events that can be queued at any time on the given session.

Table 215: VI_ATTR_MAX_QUEUE_LENGTH Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt32	1h to FFFFFFFh	50	Read/Write Local

Comments

If the number of pending occurrences exceeds the value specified in this attribute, the lowest-priority events are discarded. This attribute is

- · Read/Write until viEnableEvent() is called for the first time on a session
- · Read Only after viEnableEvent() is called for the first time on a session

See also

Setting and Retrieving Attributes viEnableEvent()

VI_ATTR_OPER_NAME

Usage

The name of the operation generating the event.

Table 216: VI_ATTR_OPER_NAME Attribute

Data Type	Range of Values	Default	Access Privilege
ViString	N/A	N/A	Read Only

Comments

This attribute is used to check the operation name that generated an event, typically an exception. For example, for an exception generated from the viLock() operation, VI_ATTR_OPER_NAME would contain the string "viLock".

See also

Setting and Retrieving Attributes

Events

VI_EVENT_EXCEPTION

VI_ATTR_RD_BUF_OPER_MODE

Usage

Determines the operational mode of the read buffer.

Table 217: VI_ATTR_RD_BUF_OPER_MODE Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt16	VI_FLUSH_ON_ACCESS	VI_FLUSH_DISABLE	Read/Write Local
	VI_FLUSH_DISABLE		

Comments

When the operational mode is set to

- VI_FLUSH_DISABLE (default), the buffer is flushed only on explicit calls to viFlush().
- VI_FLUSH_ON_ACCESS, the buffer is flushed every time a viScanf() operation completes.

See also

```
Setting and Retrieving Attributes viScanf()
```

VI_ATTR_RET_COUNT

Usage

Contains the actual number of elements that were asynchronously transferred.

Table 218: VI_ATTR_RET_COUNT Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt32	0 to FFFFFFFh	N/A	Read Only

This attribute is used to check the return count after event I/O completion.

See also

Setting and Retrieving Attributes VI_EVENT_IO_COMPLETION

VI_ATTR_RM_SESSION

Usage

Specifies the session of the Resource Manager that was used to open this session.

Table 219: VI_ATTR_RM_SESSION Attribute

Data Type	Range of Values	Default	Access Privilege
ViSession	N/A	N/A	Read Only Local

Comments

Specifies the session of the Resource Manager that was used to open this session.

See also

Setting and Retrieving Attributes

VI_ATTR_RSRC_IMPL_VERSION

Usage

Resource version that uniquely identifies each of the different revisions or implementations of a resource.

Table 220: VI_ATTR_RSRC_IMPL_VERSION Attribute

Data Type	Range of Values	Default	Access Privilege
ViVersion	0 to FFFFFFFh	N/A	Read Only Global

Comments

The value of this attribute is defined by the individual manufacturer and increments the total version value on subsequent revisions. The value of sub-minor versions is non-zero only for pre-release versions (beta). All officially released products have a sub-minor value of zero.

Table 221: ViVersion Description for VI_ATTR_RSRC_IMPL_VERSION

Bits 31 to 20	Bits 19 to 8	Bits 0 to 7
Major Number	Minor Number	Sub-minor Number

See also

Setting and Retrieving Attributes

VI_ATTR_RSRC_LOCK_STATE

Usage

The current locking state of the resource on the given session.

Table 222: VI_ATTR_RSRC_LOCK_STATE Attribute

Data Type	Range of Values	Default	Access Privilege
ViAccessMode	VI_NO_LOCK	VI_NO_LOCK	Read Only Global
	VI_EXCLUSIVE_LOCK		
	VI_SHARED_LOCK		

Comments

The resource can be unlocked, locked with an exclusive lock, or locked with a shared lock.

See also

Setting and Retrieving Attributes Locking and Unlocking Resources

VI_ATTR_RSRC_MANF_ID

Usage

A value that corresponds to the VXI manufacturer ID of the manufacturer that created the VISA implementation.

Table 223: VI_ATTR_RSRC_MANF_ID Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt16	0 to 3FFFh	N/A	Read Only Global

Comments

The manufacturer of TekVISA is Tektronix.

See also

Setting and Retrieving Attributes

VI_ATTR_RSRC_MANF_NAME

Usage

A string that corresponds to the VXI manufacturer name of the manufacturer that created the VISA implementation.

Table 224: VI_ATTR_RSRC_MANF_NAME Attribute

Data Type	Range of Values	Default	Access Privilege
ViString	N/A	N/A	Read Only Global

Comments

The manufacturer of TekVISA is Tektronix.

See also

Setting and Retrieving Attributes

VI_ATTR_RSRC_NAME

Usage

The unique identifier for a resource.

Table 225: VI_ATTR_RSRC_NAME Attribute

Data Type	Range of Values	Default	Access Privilege
ViRsrc	N/A	N/A	Read Only Global

Comments

For the Default Resource Manager, the value of this attribute is "", the empty string.

- The value of this attribute must be compliant with the address structure presented in the following table. See the viOpen() description for examples.
 - Optional string segments are shown in square brackets ([]).
 - The default value for the optional string segment board is 0.
 - The default value for the optional string segment secondary address is none.
 - Address strings are not case sensitive.

Table 226: Resource Address String Grammar

Interface	Syntax
ASRL	ASRL[board][::INSTR]
GPIB	GPIB[board]:: primary address[:: secondary address][::INSTR]

See also

Setting and Retrieving Attributes viOpen()

VI_ATTR_RSRC_SPEC_VERSION

Usage

Resource version that uniquely identifies the version of the VISA specification to which the implementation is compliant.

Table 227: VI_ATTR_RSRC_SPEC_VERSION Attribute

Data Type	Range of Values	Default	Access Privilege
ViVersion	0 to FFFFFFFh	00200000h	Read Only Global

Comments

This current implementation is compliant with Version 2.0 of the VISA Specification.

Table 228: ViVersion Description for VI_ATTR_RSRC_SPEC_VERSION

Bits 31 to 20	Bits 19 to 8	Bits 0 to 7
Major Number	Minor Number	Sub-minor Number

See also

Setting and Retrieving Attributes

VI_ATTR_SEND_END_EN

Usage

Specifies whether to assert END during the transfer of the last byte of the buffer.

Table 229: VI_ATTR_SEND_END_EN Attribute

Data Type	Range of Values	Default	Access Privilege
Vi Boolean	VI_TRUE	VI_TRUE	Read/Write Local
	VI_FALSE		

Comments

Applicable to GPIB and serial devices.

See also

Setting and Retrieving Attributes
Basic Input/Output
Reading and Writing Formatted Data

VI_ATTR_STATUS

Usage

Contains the return code of the asynchronous I/O operation that has completed or status code returned by an operation generating an error.

Table 230: VI_ATTR_STATUS Attribute

Data Type	Range of Values	Default	Access Privilege
ViStatus	N/A	N/A	Read Only

Comments

This attribute is used to check the return code after event I/O completion or the status code after an exception event.

See also

Setting and Retrieving Attributes Handling Events VI_EVENT_IO_COMPLETION VI_EVENT_EXCEPTION

VI_ATTR_SUPPRESS_END_EN

Usage

Specifies whether to suppress the END indicator termination.

Table 231: VI_ATTR_SUPPRESS_END_EN Attribute

Data Type	Range of Values	Default	Access Privilege
ViBoolean	VI_TRUE	VI_FALSE	Read/Write Local
	VI_FALSE		

Comments

If this attribute is set to

- VI_TRUE, the END indicator does not terminate read operations.
- VI_FALSE, the END indicator terminates read operations.

See also

Setting and Retrieving Attributes viRead()

VI_ATTR_TCPIP_ADDR

Usage

Specifies the TCPIP address of the device to which the session is connected. This string is formatted in dot notation.

Table 232: VI_ATTR_TCPIP_ADDR Attribute

Data Type	Range of Values	Default	Access Privilege
ViString	N/A	N/A	Read Only Global

Comments

This attribute is applicable to TCPIP INSTR and TCPIP SOCKET.

See also

Setting and Retrieving Attributes VI_ATTR_TCPIP_HOSTNAME

VI_ATTR_TCPIP_HISLIP_MAX_MESSAGE_KB

Usage

This is the maximum HiSLIP message size VISA will accept from a HiSLIP system in units of kilobytes (1024 bytes). Defaults to 1024 (a 1 MB maximum message size).

VI_ATTR_TCPIP_HISLIP_OVERLAP_EN

Usage

This enables HiSLIP 'Overlap' mode and its value defaults to the mode suggested by the instrument on HiSLIP connection.

- If disabled, the connection uses 'Synchronous' mode to detect and recover from interrupted errors.
- If enabled, the connection uses 'Overlapped' mode to allow overlapped responses. If changed, VISA will do a Device Clear operation to change the mode.

Table 233: VI_ATTR_TCPIP_HISLIP_OVERLAP_EN Attribute

VI_ATTR_TCPIP_HISLIP_OVERLAP	R/W	Local	ViBoolean	VI_TRUE, VI_FALSE
_EN				

VI_ATTR_TCPIP_HISLIP_VERSION

Usage

This is the HiSLIP protocol version used for a particular HiSLIP connection. Currently, HiSLIP version 1.0 would return a ViVersion value of 0x00100000.

Table 234: VI_ATTR_TCPIP_HISLIP_VERSION Attribute

Symbolic Name	Range	Default
VI_ATTR_TCPIP_HISLIP_VERSION	Oh to FFFFFFFh	N/A

VI_ATTR_TCPIP_HOSTNAME

Usage

Specifies the host name of the device. If no host name is available, this attribute returns an empty string.

Table 235: VI_ATTR_TCPIP_HOSTNAME Attribute

Data Type	Range of Values	Default	Access Privilege
ViString	N/A	N/A	Read Only Global

Comments

This attribute is applicable to TCPIP INSTR and TCPIP SOCKET.

See also

```
Setting and Retrieving Attributes
VI_ATTR_TCPIP_ADDR
```

VI_ATTR_TCPIP_IS_HISLIP

Usage

Specifies whether this resource uses the HiSLIP protocol.

Table 236: VI_ATTR_TCPIP_IS_HISLIP Attribute

VI_ATTR_TCPIP_IS_HISLIP	RO	Global	ViBoolean	VI_TRUE, VI_FALSE
-------------------------	----	--------	-----------	-------------------

VI_ATTR_TCPIP_KEEPALIVE

Usage

An application can request a TCP/IP provider to enable the use of keep-alive packets on TCP connections by turning on this attribute. If a connection is dropped as a result of keep-alives, the error code VI_ERROR_CONN_LOST is returned to current and subsequent I/O calls on the session.

Table 237: VI_ATTR_TCPIP_KEEPALIVE Attribute

Data Type	Range of Values	Default	Access Privilege
ViBoolean	VI_TRUE	VI_FALSE	Read/Write Local
	VI_FALSE		

This attribute is applicable to TCPIP SOCKET only.

See also

Setting and Retrieving Attributes VI_ATTR_TCPIP_NODELAY

VI_ATTR_TCPIP_NODELAY

Usage

Disables the Nagle algorithm when this attribute is enabled. The Nagle algorithm improves network performance by buffering send data until a full-size packet can be sent. This attribute is enabled by default in VISA to verify that synchronous writes get flushed immediately.

Table 238: VI_ATTR_TCPIP_NODELAY Attribute

Data Type	Range of Values	Default	Access Privilege
ViBoolean	VI_TRUE	VI_FALSE	Read/Write Local
	VI_FALSE		

Comments

This attribute is applicable to TCPIP SOCKET only.

See also

Setting and Retrieving Attributes VI_ATTR_TCPIP_KEEPALIVE

VI_ATTR_TCPIP_PORT

Usage

Specifies the port number for a given TCPIP address. For a TCPIP SOCKET resource, this is a required part of the address string.

Table 239: VI_ATTR_TCPIP_PORT Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt16	0 to FFFFh	N/A	Read Only Global

Comments

This attribute is applicable to TCPIP SOCKET only.

See also

Setting and Retrieving Attributes

VI_ATTR_TERMCHAR

Usage

Termination character.

Table 240: VI_ATTR_TERMCHAR Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt8	0 to FFh	0Ah (linefeed)	Read/Write Local

Comments

When the termination character is read and VI_ATTR_TERMCHAR_EN is enabled during a read operation, the read operation terminates.

See also

Setting and Retrieving Attributes Basic Input/Output Reading and Writing Formatted Data VI_ATTR_TERMCHAR_EN VI_ATTR_ASRL_END_IN VI_ATTR_ASRL_END_OUT viRead()

VI_ATTR_TERMCHAR_EN

Usage

Flag that determines whether the read operation should terminate when a termination character is received.

Table 241: VI_ATTR_TERMCHAR_EN Attribute

Data Type	Range of Values	Default	Access Privilege
ViBoolean	VI_TRUE	VI_FALSE	Read/Write Local
	VI_FALSE		

Comments

When the termination character is read and VI_ATTR_TERMCHAR_EN is enabled during a read operation, the read operation terminates.

See also

Setting and Retrieving Attributes Basic Input/Output Reading and Writing Formatted Data VI_ATTR_TERMCHAR

viRead()

VI_ATTR_TMO_VALUE

Usage

Minimum timeout value to use, in milliseconds.

Table 242: VI_ATTR_TMO_VALUE Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt32	VI_TMO_IMMEDIATE	2000	Read/Write Local
	1 to FFFFFFEh		
	VI_TMO_INFINITE		

Comments

A timeout value of

- VI_TMO_IMMEDIATE means that operations should never wait for the device to respond.
- VI_TMO_INFINITE disables the timeout mechanism.

See also

Setting and Retrieving Attributes

VI_ATTR_TRIG_ID

Usage

Identifier for the current triggering mechanism.

Table 243: VI_ATTR_TRIG_ID Attribute

Data Type	Range of Values	Default	Access Privilege
Vilnt16	VI_TRIG_SW	VI_TRIG_SW	Read/Write Local

Comments

Applicable to GPIB and serial devices.

See also

Setting and Retrieving Attributes viAssertTrigger()

VI_ATTR_TCPIP_IS_HISLIP

Usage

Specifies whether this resource uses the HiSLIP protocol.

Table 244: VI_ATTR_TCPIP_IS_HISLIP Attribute

20			
RO	Global	ViBoolean	VI_IRUE, VI_FALSE

VI_ATTR_USB_INTFC_NUM

Usage

Specifies the USB interface number of the device to which the session is connected.

Table 245: VI_ATTR_USB_INTFC_NUM Attribute

Data Type	Range of Values	Default	Access Privilege
vilnt16	0 to FEh	0	Read Only Global

Comments

Applicable only to USB INSTR devices.

See also

Setting and Retrieving Attributes

VI_ATTR_USB_MAX_INTR_SIZE

Usage

Specifies the maximum number of bytes that the USB device will send on the interrupt-IN pipe.

Table 246: VI_ATTR_USB_MAX_INTR_SIZE Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt16	0 to FFFFh	N/A	Read/Write Local

Comments

Applicable only to USB INSTR devices.

If a USB interrupt contains more data than this size, the data in excess of this size will be lost.

VI_ATTR_USB_MAX_INTR_SIZE is Read/Write when the corresponding session is not enabled to receive USB interrupt events. When the session is enabled to receive USB interrupt events, the attribute VI_ATTR_USB_MAX_INTR_SIZE is Read Only

See also

Setting and Retrieving Attributes

VI_ATTR_USB_PROTOCOL

Usage

Specifies the USB protocol number.

Table 247: VI_ATTR_USB_PROTOCOL Attribute

Data Type	Range of Values	Default	Access Privilege
Vilnt16	0 to FFh	N/A	Read Only Global

Comments

Applicable only to USB INSTR devices.

See also

Setting and Retrieving Attributes

VI_ATTR_USB_RECV_INTR_DATA

Usage

Specifies the actual data that was received from the USB interrupt-IN pipe.

Table 248: VI_ATTR_USB_RECV_INTR_DATA Attribute

Data Type	Range of Values	Default	Access Privilege
ViAUInt8	N/A	N/A	Read Only

Comments

Applicable only to USB INSTR devices. Contains the actual received data from the USB Interrupt. The size of the data buffer passed in must be at least equal to the value of VI_ATTR_USB_RECV_INTR_SIZE.

See also

Setting and Retrieving Attributes

VI_ATTR_USB_RECV_INTR_SIZE

Usage

Specifies the size of the data that was received from the USB interrupt-IN pipe.

Table 249: VI_ATTR_USB_RECV_INTR_SIZE Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt16	0 to FFFFh	N/A	Read/Write Local

Applicable only to USB INSTR devices. Contains the number of bytes of USB interrupt data that is stored.

See also

Setting and Retrieving Attributes VI_ATTR_USB_RECV_INTR_DATA

VI_ATTR_USB_SERIAL_NUM

Usage

This string attribute is the serial number of the USB instrument. The value of this attribute should be used only for display purposes and not for programmatic decisions.

Table 250: VI_ATTR_USB_SERIAL_NUM Attribute

Data Type	Range of Values	Default	Access Privilege
viString	N/A	N/A	Read Only Global

Comments

Applicable only to USB INSTR devices.

See also

Setting and Retrieving Attributes

VI_ATTR_USER_DATA

Usage

Data used privately by the application for a particular session.

Table 251: VI_ATTR_USER_DATA Attribute

Data Type	Range of Values	Default	Access Privilege
ViAddr	N/A	N/A	Read/Write Local

Comments

This data is not used by VISA for any purpose and is provided to the application for its own use.

See also

Setting and Retrieving Attributes

VI_ATTR_WR_BUF_OPER_MODE

Usage

Determines the operational mode of the write buffer.

Table 252: VI_ATTR_WR_BUF_OPER_MODE Attribute

Data Type	Range of Values	Default	Access Privilege
ViUInt16	VI_FLUSH_ON_ACCESS	VI_FLUSH_WHEN_FULL	Read/Write Local
	VI_FLUSH_WHEN_FULL		

Comments

When the operational mode is set to

- VI_FLUSH_WHEN_FULL (default), the buffer is flushed when an END indicator is written to the buffer, or when the buffer fills up.
- VI_FLUSH_ON_ACCESS, the write buffer is flushed under the same conditions, and also every time a viPrintf() operation completes.

See also

Setting and Retrieving Attributes Basic Input/Output Reading and Writing Formatted Data viPrintf()

Events

The following event types are presented in alphabetical order.

VI_EVENT_EXCEPTION

Usage

Notification that an error condition has occurred during an operation invocation.

Table 253: VI_EVENT_EXCEPTION related attributes

Event attribute	Description
VI_ATTR_EVENT_TYPE	Unique logical identifier of the event. Value = VI_EVENT_EXCEPTION.
VI_ATTR_STATUS	Status code returned by the operation generating the error.
VI_ATTR_OPER_NAME	The name of the operation generating the event.

See also

Exception Handling

Generating an Error Condition

VI_EVENT_IO_COMPLETION

Usage

Notification that an asynchronous operation has completed.

Table 254: VI_EVENT_IO_COMPLETION related attributes

Event attribute	Description	
VI_ATTR_EVENT_TYPE	Unique logical identifier of the event.	
	Value = VI_EVENT_IO_COMPLETION.	
VI_ATTR_STATUS	Return code of the asynchronous I/O operation that has completed.	
VI_ATTR_JOB_ID	The job ID of the asynchronous operation that has completed.	
VI_ATTR_BUFFER	The address of a buffer that was used in an asynchronous operation.	
VI_ATTR_RET_COUNT	The actual number of elements that were asynchronously transferred.	
VI_ATTR_OPER_NAME	The name of the operation generating the event.	

See also

Asynchronous Read/Write viReadAsync() viWriteAsync

VI_EVENT_SERVICE_REQ

Usage

Notification that a service request was received from the device.

Table 255: VI_EVENT_SERVICE_REQ related attributes

Event attribute	Description
VI_ATTR_EVENT_TYPE	Unique logical identifier of the event.
	Value = VI_EVENT_SERVICE_REQ.

See also

Status/Service Request

Programming examples

Introduction

The programming examples discussed here illustrate methods you can use to control the oscilloscope using VISA. All the program examples assume that the device descriptor is GPIB8::1::INSTR. The sample programs include:

SIMPLE.CPP — illustrates opening and closing a session

SIMPLEFINDRSRC.CPP — illustrates finding resources using regular expressions

FINDRSRCATTRMATCH.CPP — illustrates finding resources using attribute matching

ATTRACCESS.CPP - illustrates getting and setting attributes

RWEXAM.CPP — illustrates basic input/output

FORMATIO.CPP — illustrates formatted input/output

BUFFERIO.CPP - demonstrates the performance effect of resizing the formatted I/O buffers

SRQWAIT.CPP — illustrates event handling using the queuing mechanism

SRQ.CPP — illustrates event handling using the callback mechanism

EXLOCKEXAM.CPP — illustrates exclusive locking of resources

SHAREDLOCK.CPP — illustrates shared locking of resources

The sample programs were written in Microsoft Visual C ++ 6.0. If you wish to develop code, you will need to compile and link using two Visual C++ files: visa32.lib and visa.h. If you have TekVISA (or any version of VISA) installed on your computer, these files can be found in the C:\vxipnp\winnt directory.

- The visa32.lib file is located in the \lib\Msc subdirectory of the C:\vxipnp\winnt directory.
- The visa.h file is located in the \include subdirectory of the C:\vxipnp\winnt directory.

For more information about TekVISA installation and packaging, refer to the Getting Started chapter of this book, and the README.PDF file that accompanies the TekVISA installation software on the Product Software CD for your Tektronix instruments.

Compiling and linking examples

 \wedge

Notice: Some project examples in this chapter have already been configured and compiled on the accompanying CD.

To make an executable for any of the files (for example, a project named SIMPLE), perform the following steps:

- 1. Install TekVISA if necessary.
- 2. Install Visual C++ if necessary.
- 3. If necessary, copy the programming example files to your hard disk.
- 4. Set up a project for each example. The example below creates a new project for the SAMPLE example program.
 - a. Invoke Visual C++.
 - b. From the File menu, select New.
 - c. From the Projects tab, Choose Win32 Console Application.
 - d. Select the directory where you want to store the project, give the project a name, for example, Simple, and click OK.
 - e. Select An Empty Project, click Finish and OK.

- f. From the Project menu, select Add to Project > Files..., navigate to the folder where you stored the Simple.cpp source file, select it, and click OK.
- 5. From the **Project** menu, select **Settings**.
- 6. Select All Configurations in the Settings for combo box.
- 7. From the C/C++ tab:
 - a. Choose the Precompiled Headers category and select Not using headers.
 - **b.** Choose the **Preprocessor** category and under the heading **Additional Include directories**, type c:\vxipnp\win95\include (or c:\vxipnp\winNT\include if you are running under Windows NT)
- 8. From the Link tab:
 - a. Choose the General category and under the heading Object/library modules, add visa32.lib to the list of files in the text entry box.
 - **b.** Choose the Input category and under the heading Additional library path, type c:\Program Files\IVI Foundation\VISA\WinNT\lib\msc and click OK.
- 9. To compile and link your sample program, choose Build from the Build menu or press F7.
- 10. To run the sample program, choose Execute from the Build menu or press Ctrl+F7.

Opening and closing sessions

The VISA Resource Manager assigns unique resource addresses and IDs and provides access to resources registered with it. Currently, one such manager is available by default to a VISA application after initialization—the Default Resource Manager. The Default Resource Manager is used when finding available resources, opening resources, and performing other operations at the resource level.

- Applications use the viOpenDefaultRM() function to get access to the Default Resource Manager. This function must be called before any VISA operations can be invoked.
 - The first call to this function initializes the VISA system, including the Default Resource Manager resource, and returns a session to that resource.
 - · Subsequent calls to this function return unique sessions to the same Default Resource Manager resource.
- After opening the Default Resource Manager, applications use the viOpen() operation to get access to a particular instrument resource. This operation opens a session to a device resource that is uniquely identified by an address string. TekVISA supports the following address string grammar syntax for GPIB and serial devices:
 - GPIB[board]::primaryaddress[::secondaryaddress][::INSTR]
 - ASRL[board][::INSTR]
 - USB[board]::manufacturer ID::model code::serial number[::USB interface number]
 [::INSTR]

where brackets [] enclose optional fields, the default board is 0, and the default secondary address is None. For example, GPIB8 refers to the GPIB INSTR device on board 0 at primary address 8.

- Once an application has opened a session to a VISA resource using some of the services in the VISA Resource Manager, it can use viClose() to close that session and free up all the system resources associated with it. The VISA system is also responsible for freeing up all associated system resources whenever an application becomes dysfunctional.
- IF the viClose() operation is invoked on a session returned from viOpenDefaultRM(), all VISA sessions opened with the corresponding Default Resource Manager session are also closed.

SIMPLE.CPP example

The following C++ example, **SIMPLE.CPP**, opens the Default Resource Manager, opens a session to a GPIB device, queries the device, and then closes the session to the GPIB device and closes the session to the Default Resource Manager. Note that the first Close() operation is optional and not really necessary, since closing the Default Resource Manager also closes any sessions opened with it.

```
#include <visa.h>
#include <stdio.h>
#include <memory.h>
// This example opens a specific GPIB device, does an *idn query
// and prints the result.
int main(int argc, char* argv[])
ł
   ViSession rm = VI NULL, vi = VI NULL;
  ViStatus status;
  ViChar buffer[256];
  ViUInt32 retCnt;
  // Open a default session
  status = viOpenDefaultRM(&rm);
  if (status < VI SUCCESS) goto error;
  // Open the GPIB device at primary address 1, GPIB board 8 status = viOpen(rm, "GPIB8::1::INSTR",
VI NULL, VI NULL,&vi);
  if (status < VI SUCCESS) goto error;
  // Send an ID query.
     status = viWrite(vi, (ViBuf) "*idn?", 5, &retCnt);
  if (status < VI SUCCESS) goto error;
  // Clear the buffer and read the response
     memset(buffer, 0, sizeof(buffer));
     status = viRead(vi, (ViBuf) buffer, sizeof(buffer), &retCnt);
  if (status < VI SUCCESS) goto error;
  // Print the response
     printf("id: %s\n", buffer);
  // Clean up
  viClose(vi); // Not needed, but makes things a bit more
  // understandable
  viClose(rm); // Closes resource manager and any sessions
  // opened with it
  return 0;
  error:
  // Report error and clean up
  viStatusDesc(vi, status, buffer);
  fprintf(stderr, "failure: %s\n", buffer);
  if (rm != VI NULL) {
     viClose(rm);
  }
  return 1;
}
```

Finding resources

The VISA Resource Manager resource gives applications the ability to search a VISA system for a resource in order to establish a communication link to it. Applications can request this service by using the **viFindRsrc()** and **viFind-Next()** operations.

- The viFindRsrc() operation matches an expression against the resources available for a particular interface. The search is based on
 a resource address string that uniquely identifies a given resource in the system. Search criteria can include a regular expression
 matched against the address strings of available resources, and an optional attribute expression involving logical comparisons of
 attribute values. If the match is successful, viFindRsrc() returns a handle to a find list as well as the first resource found in the list,
 along with a count to indicate if more matching resources were found for the designated interface. The find list handle must be used as
 an input to viFindNext().
- · The viFindNext() operation receives the find list handle created by viFindRsrc() and returns the next device resource found in the list.
- When the find list handle is no longer needed, it should be passed to viClose(). The viClose() operation is used not only to close sessions, but also to free find lists returned from the viFindRsrc() operation, as well as events returned from the viWaitOnEvent() operation.

Using regular expressions

A regular expression is a string used for pattern matching against the resource address strings known to the VISA Resource Manager. The expression can include regular characters as well as wildcard characters such as ?. Given a regular expression as input, the **viFindRsrc()** operation compares it to a resource string or list of strings, and returns a list of one or more strings that match the regular expression.

SIMPLEFINDRSRC.CPP example

The following C++ example, SIMPLEFINDRSRC.CPP, opens the Default Resource Manager, finds all available GPIB devices, opens a session to the first one, prints its response to an ID query, closes the session, finds the next one, and so on for all GPIB devices found. At the end of the example, the program closes the session to the Default Resource Manager.

```
#include <visa.h>
#include <stdio.h>
#include <memory.h>
// This example cycles through all GPIB devices and prints out
// each instrument's response to an *idn? query.
int main(int argc, char* argv[])
ł
  ViSession rm = VI NULL, vi = VI NULL;
  ViStatus status;
  ViChar desc[256], id[256], buffer[256];
  ViUInt32 retCnt, itemCnt;
  ViFindList list:
  ViUInt32 i;
  // Open a default session
  status = viOpenDefaultRM(&rm);
  if (status < VI SUCCESS) goto error;
  // Find all GPIB devices
  status = viFindRsrc(rm, "GPIB?*INSTR", &list, &itemCnt,desc);
  if (status < VI SUCCESS) goto error;
  for (i = 0; i < itemCnt; i++) {
     // Open resource found in rsrc list
     status = viOpen(rm, desc, VI NULL, VI NULL, &vi);
     if (status < VI SUCCESS) goto error;
     // Send an ID query.
     status = viWrite(vi, (ViBuf) "*idn?", 5, &retCnt);
     if (status < VI SUCCESS) goto error;
     // Clear the buffer and read the response
     memset(id, 0, sizeof(id)):
     status = viRead(vi, (ViBuf) id, sizeof(id), &retCnt);
     if (status < VI SUCCESS) goto error;
```

```
// Print the response
     printf("id: %s: %s\n", desc, id);
     // We're done with this device so close it
     viClose(vi):
     // Get the next item
     viFindNext(list, desc);
  }
  // Clean up
  viClose(rm);
  return 0;
error:
  // Report error and clean up
  viStatusDesc(vi, status, buffer);
  fprintf(stderr, "failure: %s\n", buffer);
  if (rm != VI NULL) {
     viClose(rm);
  }
  return 1;
}
```

Using attribute matching

If the resource string matches the regular expression, the attribute values of the resource are then matched against an optional attribute expression if one exists. This expression can include the use of logical ANDs, ORs and NOTs. Equal (==) and unequal (!=) comparators can be used to compare attributes of any type, and other inequality comparators (>, <, >=, <=) can be used to compare attributes of numeric type. If the attribute type is ViString, a regular expression can be used in matching the attribute. Only global attributes can be used in the attribute expression.

FINDRSRCATTRMATCH.CPP example

The following C++ example, **FINDRSRCATTRMATCH.CPP**, opens the Default Resource Manager, finds all GPIB devices with primary addresses between 1 and 5, then cycles through the find list and, for each found device, opens a session, print its response to an ID query, and closes the session. At the end of the example, the program closes the session to the Default Resource Manager.

```
#include <visa.h>
#include <stdio.h>
#include <memory.h>
// This example cycles through all GPIB devices with primary address
// between 1 and 5 and prints out each instrument's response to an
// *idn? query.
int main(int argc, char* argv[])
ł
  ViSession rm = VI NULL, vi = VI NULL;
  ViStatus status;
  ViChar desc[256], id[256], buffer[256];
  ViUInt32 retCnt, itemCnt;
  ViFindList list;
  ViUInt32 i;
  // Open a default session
  status = viOpenDefaultRM(&rm);
  if (status < VI SUCCESS) goto error;
```

```
// Find all GPIB devices
  status = viFindRsrc(rm, "GPIB?*INSTR\{VI_ATTR_GPIB_PRIMARY_ADDR >= 1\&&
VI_ATTR_GPIB_PRIMARY_ADDR <= 5}",&list, &itemCnt, desc);</pre>
  if (status < VI SUCCESS) goto error;
  for (i = 0; i < itemCnt; i++) {
    // Open resource found in rsrc list
    status = viOpen(rm, desc, VI NULL, VI NULL, &vi);
    if (status < VI SUCCESS) goto error;
    // Send an ID query.
    status = viWrite(vi, (ViBuf) "*idn?", 5, &retCnt);
    if (status < VI SUCCESS) goto error;
    // Clear the buffer and read the response
    memset(id, 0, sizeof(id));
    status = viRead(vi, (ViBuf) id, sizeof(id), &retCnt);
    if (status < VI SUCCESS) goto error;
    // Print the response
    printf("id: %s: %s\n", desc, id);
    // We're done with this device so close it
    viClose(vi);
    // Get the next item
    viFindNext(list, desc);
  }
  // Clean up
  viClose(rm);
  return 0;
error:
  // Report error and clean up
  viStatusDesc(vi, status, buffer);
  fprintf(stderr, "failure: %s\n", buffer);
  if (rm != VI NULL) {
    viClose(rm);
  }
  return 1;
}
```

Setting and retrieving attributes

Resources have attributes associated with them. Some attributes depict the instantaneous state of the resource and some define changeable parameters that can be used to modify the behavior of the resources. VISA defines operations for retrieving and modifying the value of individual resource attributes.

Retrieving attributes

The VISA operation for retrieving the value of an attribute is viGetAttribute().

Setting attributes

The VISA operation for modifying the value of an attribute is viSetAttribute().

ATTRACCESS.CPP example

The following C++ example, **ATTRACCESS.CPP**, opens the Default Resource Manager, gets some information about the VISA implementation, then opens a session to a particular GPIB device (the GPIB INSTR device on board 8 at primary address 1), sets the timeout to 5 seconds, queries the device ID, and prints the results. At the end of the example, the program closes the sessions to the device and to the Default Resource Manager.

In this example, the program uses the **viGetAttribute()** operation to retrieve VISA implementation information. Specifically, the program consults the VI_ATTR_RSRC_MANF_NAME, VI_ATTR_RSRC_SPEC_VERSION, and VI_ATTR_RSRC_IMPL_VERSION attribute values to obtain the VISA Manufacturer name, the VISA specification version it supports, and the VISA implementation version.

In this example, the program uses the **viSetAttribute()** operation to set the timeout to 5 seconds. Specifically, the program sets the VI_ATTR_TMO_VALUE to 5000 milliseconds, which corresponds to 5 seconds.

```
#include <visa.h>
#include <stdio.h>
#include <memory.h>
// This example gets some info about the VISA implementation,
// opens a specific GPIB device, sets the timeout to 5 seconds, and
// does an *idn query then prints the result.
int main(int argc, char* argv[])
ł
  ViSession rm = VI NULL, vi = VI NULL;
  ViStatus status;
  ViChar buffer[256];
  ViUInt32 retCnt;
  ViVersion version = 0, impl = 0;
  // Open a default session
  status = viOpenDefaultRM(&rm);
  if (status < VI SUCCESS) goto error;
  // Get and print VISA's vendors name, VISA Specification
  // Version, and implementation version.
  status = viGetAttribute(rm, VI ATTR RSRC MANF NAME, buffer);
  if (status < VI SUCCESS) goto error;
  status = viGetAttribute(rm, VI ATTR RSRC SPEC VERSION,&version);
  if (status < VI SUCCESS) goto error;
  status = viGetAttribute(rm, VI ATTR RSRC IMPL VERSION,&impl);
  if (status < VI SUCCESS) goto error;
  printf("VISA Manufacturer Name: %s, supports %x spec,%x implementation version\n", buffer, version, impl);
```

```
// Open the GPIB device at primary address 1, GPIB board 8status = viOpen(rm, "GPIB8::1::INSTR", VI_NULL,
VI_NULL,&vi);
```

if (status < VI_SUCCESS) goto error;

```
// Set timeout to 5 seconds
status = viSetAttribute(vi, VI_ATTR_TMO_VALUE, 5000);
```

```
if (status < VI SUCCESS) goto error;
  // Send an ID query.
  status = viWrite(vi, (ViBuf) "*idn?", 5, &retCnt);
  if (status < VI SUCCESS) goto error;
  // Clear the buffer and read the response
  memset(buffer, 0, sizeof(buffer));
  status = viRead(vi, (ViBuf) buffer, sizeof(buffer), &retCnt);
  if (status < VI SUCCESS) goto error;
  // Print the response
  printf("id: %s\n", buffer);
  // Clean up
  viClose(vi); // Not needed, but makes things a bit more
       // understandable
  viClose(rm);
  return 0:
error:
  // Report error and clean up
  viStatusDesc(vi, status, buffer);
  fprintf(stderr, "failure: %s\n", buffer);
  if (rm != VI NULL) {
    viClose(rm);
  }
  return 1;
```

```
}
```

Basic Input/Output

The VISA INSTR resource provides a program with Basic Input/Output services to

- · Send blocks of data to a device
- Request blocks of data from a device
- Send the device clear command to a device
- Trigger a device
- · Find information about a device's status

Reading and Writing Data

The Basic Input/Output Services allow devices associated with an INSTR resource to read and write data synchronously or asynchronously. The resource can receive and send data in the native mode of the associated interface, or in any alternate mode supported by the interface.

The VISA Write Service lets a program send blocks of data from an explicit user-specified buffer to the device. The device can interpret the data as necessary—for example, as messages, commands, or binary encoded data. Setting the appropriate attribute modifies the data transmittal method and other features such as whether to send an END indicator with each block of data.

The VISA Read Service lets a program request blocks of data from the device. The data is returned in an explicit, user--specified buffer. How the returned data is interpreted depends on how the device has been programmed. For example, the information could be messages, commands, or binary encoded data. Setting the appropriate attribute modifies the data transmittal method and other features such as the termination character.

Synchronous Read/Write

The basic synchronous I/O operations are viRead() and viWrite().

Extract from SIMPLE.CPP Example

The following extract from the SIMPLE.CPP example highlights the synchronous read/write portions of that example. Here, the program sends a 5--byte ID query (*idn?) to a GPIB device using a user--specified buffer, then clears the buffer for readability and reads the device's ID response from the same buffer.

```
// Send an ID query.
status = viWrite(vi, (ViBuf) "*idn?", 5, &retCnt);
if (status < VI SUCCESS) goto error;</pre>
```

// Clear the buffer and read the response memset(buffer, 0, sizeof(buffer)); status = viRead(vi, (ViBuf) buffer, sizeof(buffer), &retCnt); if (status < VI_SUCCESS) goto error;</pre>

// Print the response
printf("id: %s\n", buffer);

RWEXAM.CPP Example

In the following RWEXAM.CPP example, the program sends a 5-byte ID query (*idn?) to a GPIB device using a user-specified buffer, then reads the device's ID response from the same buffer. In this case, unlike the previous example the buffer is not cleared before it is read.

```
#include <stdio.h>
#include "visa.h"
int main(int argc, char* argv[])
{
    ViSession rm, vi;
    ViSession rm, vi;
    ViStatus status;
    char string[256];
    ViUInt32 retCnt;
    status = viOpenDefaultRM(&rm);
    if (status < VI_SUCCESS) goto error;
    status = viOpen(rm, "GPIB8::1::INSTR", NULL, NULL, &vi);
    if (status < VI_SUCCESS) goto error;
    status = viWrite(vi, (ViBuf) "*idn?", 5, &retCnt);
    if (status < VI_SUCCESS) goto error;
    status = viRead(vi, (ViBuf) string, 256, &retCnt);</pre>
```

```
if (status < VI_SUCCESS) goto error;
printf("*idn response %s\n", string);
viClose(vi);
viClose(rm);
return 0;
error:
viStatusDesc(rm, status, string);
fprintf(stderr, "Error: %s\n", (ViBuf) string);
return 0;
}
```

Asynchronous Read/Write

Any INSTR resources can have asynchronous, non-blocking operations associated with them. The basic asynchronous I/O operations are **viReadAsync()** and **viWriteAsync()**. These operations are invoked just like other operations. However, instead of waiting for the actual job to be done, they simply register the job to be done and return immediately. When I/O is complete, an event is generated to indicate the completion status.

Before beginning an asynchronous transfer, you must enable the session for the I/O completion event using the viEnableEvent() operation. After the transfer, you can use the viWaitOnEvent() operation to wait for the VI_EVENT_IO_COMPLETION event.

If you want to abort such an asynchronous operation after a specified time period, use **viTerminate()** with the unique job ID returned from the session of the operation to be aborted. If a VI_EVENT_IO_COMPLETION event has not yet occurred for the specified jobId, the **viTerminate()** operation raises a VI_EVENT_IO_COMPLETION event.

Clear

The VISA Clear Service lets a program send the device clear command to the device it is associated with. The action that the device takes depends on the interface to which it is connected. For a GPIB device, this amounts to sending the IEEE 488.1 SDC (04h) command. For a serial device, the string "*CLS\n" is sent if 488-style protocol is being used.

Invoking a viClear() operation on a device resource not only resets the hardware, it also flushes the formatted I/O read buffer (applies it to the hardware) and discards the contents of the formatted I/O write buffer used by the Formatted I/O Services for that session.

Trigger

The VISA Trigger Service provides monitoring and control access to the trigger of the device associated with the resource. Specifically, the **viAssertTrigger()** operation handles assertion of software triggers for GPIB and serial devices.

Status/Service Request

The VISA Status/Service Request Service allows a program to service requests made by other requesters in a system, and can procure device status information. Your program can determine if an event is a service request by using the **viGetAttribute()** operation to get the value of the VI_ATTR_EVENT_TYPE attribute. A related activity is to use the **viWaitOnEvent()** operation to wait on the VI_EVENT_SERVICE_REQUEST event. You can then use the **vi-ReadSTB()** operation to manually obtain device status information by reading the status byte of the service request. For example, you might read this byte to determine which GPIB device among several possibilities is making the request. If the resource cannot obtain the status information from the requester in the timeout period, it returns a timeout.

Asynchronous Read/Write

Any INSTR resources can have asynchronous, non-blocking operations associated with them. The basic asynchronous I/O operations are viReadAsync() and viWriteAsync(). These operations are invoked just like other operations. However, instead of waiting for the actual job

to be done, they simply register the job to be done and return immediately. When I/O is complete, an event is generated to indicate the completion status.

Before beginning an asynchronous transfer, you must enable the session for the I/O completion event using the **viEnableEvent()** operation. After the transfer, you can use the **viWaitOnEvent()** operation to wait for the VI_EVENT_IO_COMPLETION event.

If you want to abort such an asynchronous operation after a specified time period, use **viTerminate()** with the unique job ID returned from the session of the operation to be aborted. If a VI_EVENT_IO_COMPLETION event has not yet occurred for the specified jobId, the viTerminate() operation raises a VI_EVENT_IO_COMPLETION event.

Clear

The VISA Clear Service lets a program send the device clear command to the device it is associated with. The action that the device takes depends on the interface to which it is connected. For a GPIB device, this amounts to sending the IEEE 488.1 SDC (04h) command. For a serial device, the string "*CLS\n" is sent if 488-style protocol is being used.

Invoking a viClear() operation on a device resource not only resets the hardware, it also flushes the formatted I/O read buffer (applies it to the hardware) and discards the contents of the formatted I/O write buffer used by the Formatted I/O Services for that session.

Trigger

The VISA Trigger Service provides monitoring and control access to the trigger of the device associated with the resource. Specifically, the **viAssertTrigger()** operation handles assertion of software triggers for GPIB and serial devices.

Status/Service request

The VISA Status/Service Request Service allows a program to service requests made by other requesters in a system, and can procure device status information. Your program can determine if an event is a service request by using the viGetAttribute() operation to get the value of the VI_ATTR_EVENT_TYPE attribute. A related activity is to use the viWaitOnEvent() operation to wait on the VI_EVENT_SERVICE_REQUEST event. You can then use the vi-ReadSTB() operation to manually obtain device status information by reading the status byte of the service request. For example, you might read this byte to determine which GPIB device among several possibilities is making the request. If the resource cannot obtain the status information from the requester in the timeout period, it returns a timeout.

Reading and writing formatted data



Note: In version 1.1 and earlier versions of TekVISA, the operations described in this section return the value **NOT IMPLEMENTED**.

Buffering can improve performance and throughput by making it possible to transfer large blocks of data to and from devices at certain times. The Formatted I/O Services support formatting and intermediate buffering in two ways:



Note: These distinctions are analogous to the differences in syntax between the formatted I/O operation **fprint()** (implicit buffering held by a file pointer) and buffered I/O operation **sprint()** (explicit user-specified buffering) in the ANSI C/C++ languages.

The TekVISA formatted I/O operations write to an implicit write buffer and read from an implicit read buffer associated with a virtual instrument. These operations include viPrintf(), viScanf(), viQueryf(), and the related variable list operations (viVPrintf(), viVScanf(), and ViVQueryf()). In this document, these implicit buffers that are held by a file pointer are called the formatted I/O buffers.

The related operations viSetBuf(), viBufRead(), viBufWrite(), and viFlush() can also act on these implicit buffers to set the buffer size, read and write segments of the buffer, and flush the contents (by applying them to the hardware in the case of the read buffer, or discarding them in the case of the write buffer).

Invoking a viClear() operation on a device resource not only resets the hardware, it also flushes the formatted I/O read buffer (applies it to the hardware) and discards the contents of the formatted I/O write buffer used by the formatted I/O operations for that session.

• The TekVISA buffered I/O operations write formatted information to and read it from explicit user-supplied buffers that you provide. These operations include viSPrintf(), viSScanf() and the related variable list operations (viVSPrintf(), and viVSScanf()).

The related operations viBufRead() and viBufWrite() can also act on these explicit buffers to read data segments from a device into a user-supplied buffer, and write data segments from a user-supplied buffer to a device.

Since all of these operations actually use the **viWrite()** and **viRead()** operations to perform low-level I/O to and from the device, you are discouraged from mixing the **viWrite()** and **viRead()** basic I/O operations with formatted I/O and/or buffered I/O operations in the same session. If you do mix these operations, you must be careful to flush buffers correctly when moving between operations. It illustrates the various types of formatted read/write operations supported by VISA.




Figure 6: Types of formatted read/Write operations

Formatted I/O operations

The TekVISA formatted I/O operations write to an implicit write buffer and read from an implicit read buffer associated with a virtual instrument. Usage of these operations is illustrated in the following example.

FORMATIO.CPP example

The following C++ example, **FORMATIO.CPP**, includes a main program that opens the Default Resource Manager, opens a session to the GPIB device with primary address 1 on board 8, calls the **ReadWaveform()** function to get header and waveform data from a Tektronix TDS scope, then writes the response to the standard output, and closes the session. At the end of the example, the program closes the session to the Default Resource Manager.

To review the use of Tektronix TDS scope commands and formatted I/O operations in more detail:

1. The header off command sent using the viPrintf() operation causes the oscilloscope to omit headers on query responses, so that only the argument is returned. The \n format string sends the ASCII LF character and END identifier.

- 2. The hor: reco? query sent using the viQueryf() operation asks the oscilloscope for the current horizontal record length and receives the response. The \n format string sends the ASCII LF character and END identifier. The %Id modifier and format code specify that the argument is a long integer.
- 3. The data:start %d;data:stop %d\n commands sent using the viPrintf() operation set the starting data point to 0 and the ending data point to the record length 1 for the waveform transfer that will be initiated later using a CURVE? query. The %d format codes specify that the arguments are integers. The \n format string sends the ASCII LF character and END identifier.
- 4. The WFMOUTPRE: YOFF?\n query sent using the viQueryf() operation asks the oscilloscope for the vertical offset (YOFF) and receives the response. This information is needed to convert digitizing units to vertical units (typically volts) in order to scale the data. The %f format code specifies that the argument is a floating point number. The \n format string sends the ASCII LF character and END identifier.
- 5. The WFMOutpre:YMULT?\n query sent using the viQueryf() operation asks the oscilloscope for the vertical scale factor (YMULT) per digitizing level (also called the Y multiple) vertical multiplier and receives the response. This information is needed to convert digitizing units to vertical units (typically volts) in order to scale the data. The %f format code specifies that the argument is a floating point number. The \n format string sends the ASCII LF character and END identifier.
- 6. The DATA: ENCDG RIBINARY; WIDTH 1\n command sent using the viPrintf() operation sets the data format for the waveform transfer to binary using signed integer data--point representation, with the most significant byte transferred first. The DATA:WIDTH command sets the number of bytes to transfer to one byte per data point. The \n format string sends the ASCII LF character and END identifier.

#<a><bbb><data><newline>

Where:

a = the number of b bytes

bbb = the number of bytes to transfer

data = the curve data

newline = a single-byte new-line character at the end

- 7. The CURVE?\n query sent using the viPrintf() operation asks the oscilloscope to transfer the waveform. The \n format string sends the ASCII LF character and END identifier. Since the waveform could easily exceed the size of the formatted I/O read buffer, a viQueryf() is not being used here. Instead, we want to split up the write (viPrintf()) and read (viScanf()) operations, rather than combining them in a single query.
- 8. The viFlush(vi, VI_WRITE_BUF | VI_READ_BUF_DISCARD) operation performs two combined tasks before getting the oscilloscope's response to the CURVE? query. It transfers the contents of the formatted I/O write buffer (in this case, the CURVE? query) to the oscilloscope, and discards the contents of the formatted I/O read buffer. This flushing operation should always be performed before a viScanf() operation that follows a viPrintf() or viBufWrite() operation, to guarantee that flushing occurs.
- 9. The first viScanf(vi, "%c", &c)operation reads the first character of the waveform response from the oscilloscope. The %c format code specifies that the argument is a character. This character is expected to be #.
- 10. The second viScanf(vi, "%c", &c)operation reads the next character of the waveform response from the oscilloscope. This character specifies the width of the next field, which contains the number of bytes of waveform data to transfer, and is expected to be between 0 and 9.
- 11. The third viScanf(vi, "%c", &c)operation reads the characters that represent the number of bytes to transfer. The result of the previous scan is used as the counter in the FOR loop. Each character read is expected to be between 0 and 9.
- 12. The program uses the results of the previous scan to allocate the right size for an array of double--word floating--point numbers that will contain the waveform. Then the fourth viScanf(vi, "%c", &c) operation reads the waveform itself, using the result of the previous scan as the counter in the FOR loop. The viScanf() operation accepts input until an END indicator is read or all the format specifiers in the format string are satisfied.

13. The ptr[i] = (((double) c) - yoffset) * ymult; calculation converts the waveform data results from string data into a numerical array of double-word floating point numbers, and also converts the data from digitizing units into vertical units (typically volts in the case of waveform data).

#include <stdio.h>
#include <stdib.h>
#include <stdlib.h>
#include <assert.h>
// This function reads the currently selected waveform and returns
// it as an array of doubles.
 double* ReadWaveform(ViSession vi, long* elements) {
 ViStatus status;
 float yoffset, ymult;
 ViChar buffer[256];
 ViChar c;
 long count, i;
 double* ptr = NULL;
 assert(elements != NULL);
 status = viSetAttribute(vi, VI_ATTR_WR_BUF_OPER_MODE,VI_FLUSH_ON_ACCESS);
 status = viSetAttribute(vi, VI_ATTR_RD_BUF_OPER_MODE,VI_FLUSH_ON_ACCESS);

```
// Turn headers off, this makes parsing easier
status = viPrintf(vi, "header off\n");
if (status < VI_SUCCESS) goto error;</pre>
```

// Get record length value
status = viQueryf(vi, "hor:reco?\n", "%ld", elements);
if (status < VI_SUCCESS) goto error;</pre>

// Make sure start, stop values for curve query match the
// full record length
status = viPrintf(vi, "data:start %d;data:stop %d\n", 0,(*elements)-1);
if (status < VI SUCCESS) goto error;</pre>

// Get the yoffset to help calculate the vertical values.
status = viQueryf(vi, "WFMOUTPRE:YOFF?\n", "%f", &yoffset);
if (status < VI SUCCESS) goto error;</pre>

// Get the ymult to help calculate the vertical values.
status = viQueryf(vi, "WFMOutpre:YMULT?\n", "%f", &ymult);
if (status < VI SUCCESS) goto error;</pre>

// Request 8--bit binary data on the curve query
status = viPrintf(vi, "DATA:ENCDG RIBINARY;WIDTH 1\n");
if (status < VI_SUCCESS) goto error;</pre>

// Request the curve
status = viPrintf(vi, "CURVE?\n");
if (status < VI_SUCCESS) goto error;</pre>

// Always flush if a viScanf follows a viPrintf or // viBufWrite. status = viFlush(vi, VI_WRITE_BUF | VI_READ_BUF_DISCARD); if (status < VI_SUCCESS) goto error;</pre>

```
// Get first char and validate
  status = viScanf(vi, "%c", &c);
  if (status < VI SUCCESS) goto error;
  assert(c == '#');
  // Get width of element field.
  status = viScanf(vi, "%c", &c);
  if (status < VI SUCCESS) goto error;
  assert(c >= '0' && c <= '9');
  // Read element characters
  \operatorname{count} = \operatorname{c} - \operatorname{'0'};
  for (i = 0; i < \text{count}; i++) {
     status = viScanf(vi, "%c", &c);
     if (status < VI SUCCESS) goto error;
  assert(c >= '0' && c <= '9');
   }
  // Read waveform into allocated storage
  ptr = (double*) malloc(*elements*sizeof(double));
  for (i = 0; i < *elements; i++) {
     status = viScanf(vi, "%c", &c);
     if (status < VI SUCCESS) goto error;
     ptr[i] = (((double) c) -- yoffset) * ymult;
  }
  status = viFlush(vi, VI WRITE BUF | VI READ BUF DISCARD);
  if (status < VI SUCCESS) goto error;
  return ptr;
error:
  // Report error and clean up
  viStatusDesc(vi, status, buffer);
  fprintf(stderr, "failure: %s\n", buffer);
  if (ptr != NULL) free(ptr);
  return NULL;
}
// This program reads a waveform from a Tektronix
// TDS scope and writes the floating point values to
// stdout.
int main(int argc, char* argv[])
{
  ViSession rm = VI_NULL, vi = VI_NULL;
  ViStatus status;
  ViChar buffer[256];
  double* wfm = NULL;
  long elements, i;
  // Open a default session
  status = viOpenDefaultRM(&rm);
  if (status < VI SUCCESS) goto error;
  // Open the GPIB device at primary address 1, GPIB board 8
  status = viOpen(rm, "GPIB8::1::INSTR", VI_NULL, VI_NULL,&vi);
  if (status < VI SUCCESS) goto error;
  // Read waveform and write it to stdout
  wfm = ReadWaveform(vi, &elements);
  if (wfm != NULL) {
```

```
for (i = 0; i < \text{elements}; i++) {
       printf("%f\n", wfm[i]);
     }
  }
  // Clean up
  if (wfm != NULL) free(wfm);
  viClose(vi); // Not needed, but makes things a bit more
  // understandable
  viClose(rm);
  return 0:
error:
  // Report error and clean up
  viStatusDesc(vi, status, buffer);
  fprintf(stderr, "failure: %s\n", buffer);
  if (rm != VI NULL) viClose(rm);
  if (wfm != NULL) free(wfm);
  return 1:
}
```

Resizing the formatted I/O buffers

The VISA system provides separate formatted I/O read and write buffers that you can modify using the **viSetBuf()** operation. Use of these buffers is illustrated in the following example.

BUFFERIO.CPP Example

The following C++ example, **BUFFERIO.CPP**, demonstrates the performance effect of resizing the formatted I/O buffers. In this example as in the **FORMATIO.CPP** example, the main program opens the Default Resource Manager, opens a session to the GPIB device with primary address 1 on board 8, and calls the **ReadWaveform()** function to get header and waveform data from a Tektronix TDS scope.

In this case, before calling the **ReadWaveform()** function, the program starts a FOR loop that sets the read buffer size to 10, 100, 1000, and 10000 to show the effect of buffer sizes on performance. Each time through the loop, the program initializes a benchmark start time, calls the **ReadWaveform()** function five times to read segments of the waveform, and then writes the buffer size and the time required to read the buffer. After printing all the benchmark numbers for comparison, the program closes the session to the oscilloscope and closes the session to the Default Resource Manager.

```
if (ptr != NULL) free(ptr);
  return NULL;
}
// This program shows the performance effect of sizing buffers
// with buffered I/O.
int main(int argc, char* argv[])
Ł
  ViSessionrm = VI NULL, vi = VI NULL;
  ViStatus status;
  ViChar buffer[256];
  double* wfm = NULL;
  long elements, i;
  ViUInt32 bufferSize = 10;
  unsigned long start, total;
  // Open a default session
  status = viOpenDefaultRM(&rm);
  if (status < VI SUCCESS) goto error;
  // Open the GPIB device at primary address 1, GPIB board 8
  status = viOpen(rm, "GPIB8::1::INSTR", VI_NULL, VI_NULL, &vi);
  if (status < VI SUCCESS) goto error;
  // Try buffer sizes 10, 100, ..., 10000 to show effect
  // of buffer sizes on performance.
  for (bufferSize = 10; bufferSize <= 10000; bufferSize *= 10)
   ł
     // Set new buffer size
     viSetBuf(vi, VI READ BUF, bufferSize);
     // Get Start time for benchmark
     start = time(NULL);
     // Loop several times
     for (i = 0; i < 5; i++)
       wfm = ReadWaveform(vi, &elements);
     ł
     // Print results
     total = time(NULL) -- start;
       printf("bufSize %d, time %3.1fs\n", bufferSize,((double) total)/5.0);
  }
  // Clean up
  if (wfm != NULL) free(wfm);
  viClose(vi); // Not needed, but makes things a bit more
  // understandable
  viClose(rm);
  return 0:
error:
  // Report error and clean up
  viStatusDesc(vi, status, buffer);
  fprintf(stderr, "failure: %s\n", buffer);
  if (rm != VI NULL) viClose(rm);
  if (wfm != NULL) free(wfm);
```

```
return 1;
}
```

Flushing the formatted I/O buffer

The formatted I/O write buffer is maintained by the formatted I/O write operations—viPrintf(), viVPrintf(), and viBufWrite(). Flushing a write buffer immediately sends any queued data to the device. To explicitly flush the write buffer, you can call the viFlush() operation with a write flag set.

The formatted I/O read buffer is maintained by the formatted I/O read operations— viScanf(), viVScanf(), and viBufRead(). Flushing a read buffer discards the data in the read buffer. This guarantees that the next call to viScanf() (or a related buffered read operation) reads data directly from the device rather than from queued data in the read buffer. To explicitly flush the read buffer, you can call the viFlush() operation with a read flag set.

Although you can explicitly flush the buffers by calling the viFlush() operation, the buffers are flushed implicitly under some conditions. These conditions vary for the viPrintf() and viScanf() operations.

The write buffer is flushed automatically under the following conditions:

- When an END-indicator character is sent.
- When the buffer is full.
- In response to a call to viSetBuf() with the VI_WRITE_BUF flag set.

Invoking a viClear() operation on a device resource also flushes the read buffer and discards the contents of the write buffer used by the formatted I/O operations for that session. At such a time, any ongoing operation through the read/write port must be aborted.

Refer back to the **FORMATIO.CPP** example for sample usage of the **viPrintf()**, **viScanf()**, **viQueryf()**, and **viFlush()** operations with Tektronix TDS oscilloscopes.

Buffered I/O operations

A buffered I/O write operation writes formatted data to an explicit user-specifed buffer, while a buffered I/O read operation reads formatted data from an explicit user-specified buffer. These operations include viSPrintf(), viSScanf() and the related variable list operations (viVSPrintf(), and viVSScanf()).

The related operations viBufRead() and viBufWrite() can also act on these explicit buffers to read data segments from a device into a user-supplied buffer, and write data segments from a user-supplied buffer to a device.

Variable list operations

The VISA variable list operations use a pointer argument to a variable argument list, rather than the variable list itself as the argument. The VISA variable list operations include viVPrintf, viVSPrintf, viVScanf, viVSScanf, and viVQueryf. These operations are identical in operation to their ANSI C/C++ counterpart versions of variable list operations. Please refer to a C programming manual for more information.

Controlling the serial I/O buffers

You can use the **viSetBuf()** operation to control the sizes of the serial communication receive and transmit buffers. By resizing these buffers, you can realize performance improvements for serial device communication comparable to those derived from resizing the formatted I/O buffers. Refer to the section entitled **Resizing the Formatted I/O Buffers** for an example illustrating buffer resizing.

Handling events

An event is a means of communicating between a VISA resource and its applications. Typically, events occur because a condition requires the attention of applications.

VISA provides two independent mechanisms for an application to receive events: queuing and callback handling. The queuing and callback mechanisms are suitable for different programming styles:

- The queuing mechanism is generally useful for non-critical events that do not need immediate servicing. To receive events using the queuing mechanism, an application must invoke the viWaitOnEvent() operation. All of the occurrences of a specified event type are placed in a session-based event queue. There is one event queue per event type per session. The application can receive the event occurrences later by dequeuing them with the viWaitOnEvent() operation.
- The callback mechanism is useful when immediate responses are needed. To receive events using the callback mechanism, an application must install a callback handler using the **vilnstallHandler()** operation. The application is called directly by invoking a handler function that the application installed prior to enabling the event. The callback handler is invoked on every occurrence of the specified event.

By default, a session is not enabled to receive any events by either mechanism. Since these mechanisms work independently of each other, both can be enabled at the same time. An application can enable either or both mechanisms using the **viEnableEvent()** operation. The callback handling mechanism can be enabled for one of two modes: immediate callback or delayed callback queuing. The **viEnableEvent()** operation is also used to switch between the two callback modes. The **viDisableEvent()** operation is used to disable either or both mechanisms, regardless of the current state of the other.

When an application receives an event occurrence via either mechanism, it can determine information about the event by invoking viGetAttribute() on that event. When the application no longer needs the event information, it must call viClose() on that event. The viClose() operation is used not only to close sessions, but also to free events returned from the viWaitOnEvent() operation.

Queueing Mechanism

Applications can use the queuing mechanism in VISA to receive events only when it requests them. An application retrieves the event information by using the **viWaitOnEvent()** operation. If the specified event(s) exist in the queue, these operations retrieve the event information and return immediately. Otherwise, the application thread is blocked until the specified event(s) occur or until the timeout expires, whichever happens first. When an event occurrence unblocks a thread, the event is not queued for the session on which the wait operation was invoked.

Once a session is enabled for queuing, all the event occurrences of the specified event type are queued. When a session is disabled for queuing, any further event occurrences are not queued, but event occurrences that were already in the event queue are retained. The retained events can be dequeued at any time using the **viWaitOnEvent()** operation. An application can explicitly clear (flush) the event queue for a specified event type using the **viDiscardEvents()** operation.

SRQWAIT.CPP example

The following C++ example, **SRQWAIT.CPP**, demonstrates event handling using the queuing mechanism. The program begins by opening the Default Resource Manager and opening a session to the GPIB device with primary address 1 on board 8. Next the program enables notification of the VI_EVENT_SERVICE_REQ event.

The program then uses a series of viWrite() operations to send Tektronix TDS scope commands to set up the instrument. These commands do the following:

- 1. The :DATA:ENCDG RIBINARY; SOURCE CH1; START 1; STOP 500; WIDTH 2 commands do the following:
 - a. Set the data format for the waveform transfer to binary using signed integer data--point representation, with the most significant byte transferred first.
 - **b.** Set the data source to channel 1.
 - c. Set the starting data point to 0 and the ending data point to 500 for the waveform transfer that will be initiated later.
 - d. Set the number of bytes to transfer to two bytes per data point.

- 2. The :ACQUIRE:STOPAFTER SEQUENCE; REPET 0; STATE 0; MODE SAMPLE commands tell the oscilloscope to:
 - a. Acquire a single sequence (equivalent to pressing SINGLE from the front panel).
 - b. Disable repetitive mode (equivalent to setting Equivalent Time Auto/Off in the Acquisition control window).
 - c. Stop acquisition (equivalent to pressing STOP from the front panel).
 - **d.** Set the acquisition mode to sample (equivalent to selecting HORIZONTAL/ACQUISITION from the HORIZ/ACQ menu and then choosing SAMPLE from the Acquisition Mode group box.
- 3. The DESE 1;*ESE 1;*SRE 32 commands and the *CLS command tell the oscilloscope to:
 - a. Set registers to await an Operation Complete (OPC) event (bit 1) in the event queue. This event is summarized in the Event Status Bit(ESB) of the Status Byte Register.
 - b. Set the Event Status Bit (bit 5) to await a Service Request (SRQ).
 - c. Clear the event registers.
- 4. In the For loop, the :ACQUIRE:STATE 1 command starts acquisition and is equivalent to pressing the front panel RUN button or setting the state to ON.
- 5. The *OPC command generates the Operation Complete message in the Standard Event Status Register (SESR) and generates a Service Request (SRQ) when all pending operations complete. This allows programmers to synchronize operation of the oscilloscope with their application program.

After using the **viWaitOnEvent()** operation to wait for an SRQ event to occur, the program prints a success or failure message, uses the viDisableEvent() operation to disable the **VI_EVENT_SERVICE_REQ** event, closes the session to the oscilloscope, and closes the session to the Default Resource Manager.

// srqwait.cpp :Defines the entry point for the console application. // #include <stdio.h> #include <string.h> #include <windows.h> #include "visa.h" int main(int argc, char* argv[]) Ł ViSession rm, vi; ViStatus status; char string[256]; ViUInt32 retCnt; int i: ViUInt16 stb: ViEventType eventType = 0; ViEvent context = 0; status = viOpenDefaultRM(&rm); if (status < VI SUCCESS) goto error; status = viOpen(rm, "GPIB8::1::INSTR", NULL, NULL, &vi); if (status < VI SUCCESS) goto error; status = viEnableEvent(vi, VI_EVENT_SERVICE_REQ, VI_QUEUE, VI_NULL); if (status < VI SUCCESS) goto error; // Setup instrument status = viWrite(vi, (ViBuf)":DATA:ENCDG RIBINARY;SOURCE CH1;START 1;STOP 500;WIDTH 2", 56, &retCnt): if (status < VI SUCCESS) goto error;

```
status = viWrite(vi, (ViBuf)":ACQUIRE:STOPAFTER SEQUENCE;REPET 0;STATE 0;MODE SAMPLE",55,
&retCnt):
  if (status < VI SUCCESS) goto error;
  status = viWrite(vi, (ViBuf) "DESE 1;*ESE 1;*SRE 32", 21,&retCnt);
  if (status < VI_SUCCESS) goto error;
  // Do cause some srqs
  for (i = 0; i < 100; i++)
    status = viWrite(vi, (ViBuf) "*CLS", 4, &retCnt);
    if (status < VI SUCCESS) goto error;
    status = viWrite(vi, (ViBuf) ":ACQUIRE:STATE 1", 16,&retCnt);
    if (status < VI SUCCESS) goto error;
    status = viWrite(vi, (ViBuf) "*OPC", 4, &retCnt);
    if (status < VI SUCCESS) goto error;
    status = viWaitOnEvent(vi, VI EVENT SERVICE REQ,5000, &eventType, &context);
    if (status >= VI SUCCESS) {
      printf("(%d) Received SRQ\n", i);
      viClose(context);
    } else {
      viStatusDesc(vi, status, string);
      printf(
       "(%d) viWaitOnEvent Failed -- \"%s\"\n",
      string);
    viReadSTB(vi, &stb);
  // Cleanup and exit
  status = viDisableEvent(vi, VI EVENT SERVICE REQ, VI QUEUE);
  if (status < VI SUCCESS) goto error;
  viClose(vi);
  viClose(rm);
  return 0;
  error:
  viStatusDesc(rm, status, string);
  fprintf(stderr, "Error: %s\n", (ViBuf) string);
  return 0:
}
```

Callback mechanism

Applications can use the callback mechanism by installing handler functions that can be called back when a particular event type is received. The vilnstallHandler() operation can be used to install handlers to receive specified event types. The handlers are invoked on every occurrence of the specified event, once the session is enabled for the callback mechanism. One handler must be installed before a session can be enabled for sensing using the callback mechanism.

VISA allows applications to install multiple handlers for an event type on the same session. Multiple handlers can be installed through multiple invocations of the viInstallHandler() operation, where each invocation adds to the previous list of handlers. If more than one handler is installed for an event type, each of the handlers is invoked on every occurrence of the specified event(s). VISA specifies that the handlers are invoked in Last In First Out (LIFO) order.

When a handler is invoked, the VISA resource provides the event context as a parameter to the handler. The event context is filled in by the resource. Applications can retrieve information from the event context object using the viGetAttribute() operation.

An application can supply a reference to any application-defined value while installing handlers. This reference is passed back to the application as the userHandle parameter to the callback routine during handler invocation. This allows applications to install the same handler with different application-defined event contexts.

For example, an application can:

- install a handler with a fixed event context value **0x1** on a session for an event type.
- install the same handler with a different event context value, for example 0x2, for the same event type.

The two installations of the same handler are different from one another. Both handlers are invoked when the event of the given type occurs. However, in one invocation, the value passed to userHandle is **0x1** and in the other it is **0x2**. Thus, event handlers are uniquely identified by a combination of the userHandle handler address and the user event context. This identification is particularly useful when different handling methods need to be done depending on the user context data. Refer to viEventHandler(), an event service handler procedure prototype, for more information about writing an event handler.

An application may install the same handler on multiple sessions. In this case, the handler is invoked in the context of each session for which it was installed.

The callback mechanism of a particular session can be in one of three different states: handling, or suspended handling, or disabled.

- When a session transitions to the handling state, the callback handler is invoked for all the occurrences of the specified event type.
- When a session transitions to the suspended handling state, the callback handler is not invoked for any new event occurrences, but occurrences are kept in a suspended handler queue. The handler is invoked later, when a transition to the handling state occurs.

In the suspended handling state, a maximum of the VI_ATTR_MAX_QUEUE_LENGTH number of event occurrences are kept pending. If the number of pending occurrences exceeds the value specified in this attribute, the lowest-priority events are discarded. An application can explicitly clear (flush) the callback queue for a specified event type using the viDiscardEvents() operation.

• When a session transitions to the disabled state, the session ignores any new event occurrences, but any pending occurrences are retained in the queue.

SRQ.CPP example

The following C++ example, **SRQ.CPP**, demonstrates event handling using the callback mechanism. This example first defines a handler function called ServiceReqEventHandler, which simply prints a message that a service request occurred and returns successfully. The main program begins by opening the Default Resource Manager and opening a session to the GPIB device with primary address 1 on board 8. Next the program installs the **ServiceReqEventHandler** callback handler for the VI_EVENT_SERVICE_REQ event, and then enables notification of the VI_EVENT_SERVICE_REQ event.

The program then uses a series of viWrite() operations to send Tektronix TDS scope commands that do the following:

- 1. The :RECALL:SETUP FACTORY and :SELECT:CH1 1;CH2 0;CH3 0;CH4 0 commands reset the instrument to factory settings and select four channels.
- 2. The : DATA: ENCDG RIBINARY; SOURCE CH1; START 1; STOP 500; WIDTH 2 commands do the following:
 - a. Set the data format for the waveform transfer to binary using signed integer data--point representation, with the most significant byte transferred first.
 - **b.** Set the data source to channel 1.
 - c. Set the starting data point to 0 and the ending data point to 500 for the waveform transfer that will be initiated later.
 - d. Set the number of bytes to transfer to two bytes per data point.
- 3. The : ACQUIRE: STOPAFTER SEQUENCE; REPET 0; STATE 0; MODE SAMPLE commands tell the oscilloscope to:
 - **a.** Acquire a single sequence (equivalent to pressing SINGLE from the front panel).
 - b. Disable repetitive mode (equivalent to setting Equivalent Time Auto/Off in the Acquisition control window).
 - c. Stop acquisition (equivalent to pressing STOP from the front panel)

- d. Set the acquisition mode to sample (equivalent to selecting HORIZONTAL/ACQUISITION from the HORIZ/ACQ menu and then choosing SAMPLE from the Acquisition Mode group box.
- 4. The DESE 1;*ESE 1;*SRE 32 commands and the *CLS command tell the oscilloscope to:
 - a. Set registers to await an Operation Complete (OPC) event (bit 1) in the event queue. This event is summarized in the Event Status Bit(ESB) of the Status Byte Register.
 - b. Set the Event Status Bit (bit 5) to await a Service Request (SRQ).
 - c. Clear the event registers.
- 5. The : ACQUIRE : STATE RUN command starts acquisition and is equivalent to pressing the front panel RUN button.
- 6. The *OPC command generates the Operation Complete message in the Standard Event Status Register (SESR) and generates a Service Request (SRQ) when all pending operations complete. This allows programmers to synchronize operation of the oscilloscope with their application program.

After waiting long enough for an SRQ event to occur, the program disables the VI_EVENT_SERVICE_REQ event, uninstalls the ServiceReqEventHandle handler, closes the session to the oscilloscope, and closes the session to the Default Resource Manager.

```
// srq.cpp : Defines the entry point for the console application.
//
#include <stdio.h>
#include <string.h>
#include <windows.h>
#include "visa.h"
ViStatus VI FUNCH ServiceReqEventHandler(ViSession vi, ViEventType eventType, ViEvent event, ViAddr
userHandle)
ł
  printf("srq occurred\n");
  return VI SUCCESS;
int main(int argc, char* argv[])
  ViSession rm, vi;
  ViStatus status;
  char string[256];
  ViUInt32 retCnt;
  status = viOpenDefaultRM(&rm);
  if (status < VI SUCCESS) goto error;
  status = viOpen(rm, "GPIB8::1::INSTR", NULL, NULL, &vi);
  if (status < VI SUCCESS) goto error;
  // Setup and enable event handler
  status = viInstallHandler(vi, VI EVENT SERVICE REQ,
  ServiceReqEventHandler, NULL);
  if (status < VI SUCCESS) goto error;
  status = viEnableEvent(vi, VI EVENT_SERVICE_REQ, VI_HNDLR,VI_NULL);
  if (status < VI SUCCESS) goto error;
  // Setup instrument
  status = viWrite(vi, (ViBuf) ":RECALL:SETUP FACTORY", 21,&retCnt);
  if (status < VI SUCCESS) goto error;
  status = viWrite(vi, (ViBuf) ":SELECT:CH1 1;CH2 0;CH3 0;CH4 0", 31, &retCnt);
  if (status < VI SUCCESS) goto error;
```

```
status = viWrite(vi, (ViBuf) ":DATA:ENCDG RIBINARY;SOURCE CH1;START 1;STOP 500;WIDTH 2", 56, &retCnt);
```

if (status < VI_SUCCESS) goto error; status = viWrite(vi, (ViBuf) ":ACQUIRE:STOPAFTER SEQUENCE;REPET 0;STATE 0;MODE SAMPLE", 55, &retCnt); if (status < VI_SUCCESS) goto error; status = viWrite(vi, (ViBuf) "DESE 1;*ESE 1;*SRE 32", 21,&retCnt); if (status < VI_SUCCESS) goto error;</pre>

```
// Do a single acq
status = viWrite(vi, (ViBuf) "*CLS", 4, &retCnt);
if (status < VI_SUCCESS) goto error;
status = viWrite(vi, (ViBuf) ":ACQUIRE:STATE 1", 16, &retCnt);
if (status < VI_SUCCESS) goto error;
status = viWrite(vi, (ViBuf) "*OPC", 4, &retCnt);
if (status < VI_SUCCESS) goto error;</pre>
```

```
// Wait around long enough for srq event to occur
::Sleep(10000);
```

```
// Cleanup and exit
status = viDisableEvent(vi, VI_EVENT_SERVICE_REQ, VI_HNDLR);
if (status < VI_SUCCESS) goto error;
status = viUninstallHandler(vi, VI_EVENT_SERVICE_REQ,
ServiceReqEventHandler, NULL);
if (status < VI_SUCCESS) goto error;
viClose(vi);
viClose(rm);
return 0;
error:
viStatusDesc(rm, status, string);
fprintf(stderr, "Error: %s\n", (ViBuf) string);
return 0;
}</pre>
```

Exception handling

Note: In version 1.1 and earlier versions of TekVISA, support for exception handling is NOT IMPLEMENTED.

In VISA, exceptions are defined as events, and exception handling takes place using the callback mechanism. Each error condition defined by operations of resources can cause exception events. When an error occurs, normal execution of that session operation halts. The operation notifies the application of the error condition by raising an exception event (event type VI_EVENT_EXCEPTION). Raising the exception event invokes the application--specified exception callback routine(s) installed for the particular session, based on whether this exception event is currently enabled for the given session. The notification includes the cause of the error. Once notified, the application can tell the VISA system the action to take, depending on the error's severity.

Exception handling uses the same operations as those used for general event handling. Your application can install a callback handler that is invoked on an error. This installation can be done using the **viInstallHandler()** operation on a session. Once a handler is installed, a session can be enabled for exception event using the **viEnableEvent()** operation. The exception event is like any other event in VISA, except that the queuing and suspended handling mechanisms are not allowed.

When an error occurs for a session operation, the exception handler is executed synchronously; that is, the operation that caused the exception blocks until the exception handler completes its execution. When invoked, the exception handler can check the error condition and instruct the exception operation to take a specific action. For example:

- The handler can instruct the exception operation to continue normally (returning the indicated error code) or to not invoke any
 additional handlers (in the case of handler nesting).
- A given implementation may choose to provide implementation-specific return codes for users' exception handlers, and may take alternate actions based on those codes.
- A vendor-specific return code from an exception handler might cause the VISA implementation to close all sessions for the given process and exit the application.



Note: Using vendor-specific return codes makes an application incompatible with other implementations.

Generating an Error condition on asynchronous operations

One situation in which an exception event will not be generated is in the case of asynchronous operations. If the error is detected after the operation is posted (that is, once the asynchronous portion has begun), the status is returned normally via the I/O completion event (type IO_COMPLETION_EVENT). However, if an error occurs before the asynchronous portion begins (that is, the error is returned from the asynchronous operation itself), then the exception event will still be raised. This deviation is because asynchronous operations already raise an event when they complete, and this I/O completion event may occur in the context of a separate thread previously unknown to the application. In summary, a single application event handler can easily handle error conditions arising from both exception events and failed asynchronous operations.

Locking and unlocking resources

Summarize the main point of the content and explain why this information is important to understand. The content of shortdesc is rendered as the first paragraph of the topic and displays as roll-over information on links in online deliverables. Applications can open multiple sessions to a resource simultaneously and access the resource through the different sessions concurrently. However, an application accessing a resource might want to restrict other applications or sessions from accessing the same resource. For example, an application might need sole access to a resource in order to perform a sequence of writes. VISA defines a locking mechanism to restrict resource access in such special circumstances. The **viLock()** operation is used to acquire a lock on a resource and the **viUnlock()** operation is used to relinquish the lock.

The VISA locking mechanism enforces arbitration of access to resources on a per-session basis. If a session locks a resource, operations invoked on the resource through other sessions are either serviced or returned with an error, depending on the operation and the type of lock used.

If a VISA resource is not locked by any of its sessions, all sessions have full privilege to invoke any operation and update any global attributes. Sessions are not required to have locks to invoke operations or update global attributes. However, if some other session has already locked the resource, attempts to update global attributes or execute certain operations will fail.

Locking types and access privileges

VISA defines two different types of locks: exclusive locks and shared locks.

- If a session has an exclusive lock to a resource, other sessions cannot modify global attributes or invoke operations, but can still get
 attributes. Locking a resource restricts access from other sessions and prevents other sessions from acquiring an exclusive lock. In
 the case where an exclusive lock is acquired, locking a resource guarantees that operations do not fail because other sessions have
 acquired a lock on that resource.
- Shared locks are similar to exclusive locks in terms of access privileges, but can still be shared between multiple sessions. If a session
 has a shared lock to a resource, it can perform any operation and update any global attribute in that resource, unless some other
 session has an exclusive lock. Other sessions with shared locks can also modify global attributes and invoke operations. A session
 that does not have a shared lock will lack this capability.

The VI_ATTR_RSRC_LOCK_STATE attribute specifies the current locking state of a resource on a given session.

In TekVISA, only INSTR resource operations are restricted by the locking scheme. Also, not all operations are restricted by locking. Some operations may be permitted even when there is an exclusive lock on a resource. Likewise, some global attributes may not be read when there is any kind of lock on the resource. These exceptions, when applicable, are mentioned in the descriptions of individual operations and attributes in the Reference part of this manual.

EXLOCKEXAM.CPP example

The following C++ example, **EXLOCKEXAM.CPP**, demonstrates exclusive locking of a resource. In this example, if a -l is typed on the command line when the executable is invoked, the lockflag is set to TRUE. The program then opens the Default Resource Manager and opens a session to the GPIB device with primary address 1 on board 8. Next the program opens a FOR loop that will iterate 100 times.

Each time through the loop, if lockflag is TRUE, the program uses the **vilock()** operation toset an exclusive lock on the device for an infinite period of time. The program then uses a series of **viWrite()** and **viRead()** operations to send and receive Tektronix TDS scope commands and responses as follows:

- 1. The :ch1:scale? command queries the oscilloscope for the vertical scale of channel 1. Sending this command is equivalent to selecting Vertical Setup from the Vertical menu and then viewing the Scale. The program reads the response from the scope and then prints it, along with the number of times the program has been through the FOR loop.
- 2. The :ch1:position? command queries the oscilloscope for the vertical position setting for channel 1. This command is equivalent to selecting Position from the Vertical menu.vertical Position/Scale of channel 1. The program reads the response from the scope and then prints it, along with the number of times the program has been through the FOR loop.

Each time through the loop, the program unlocks the device using the **viUnlock()** operation. Once the program exits the FOR loop, it closes the session to the oscilloscope, and closes the session to the Default Resource Manager.

```
#include <stdio.h>
#include <stdlib.h>
#include "visa.h"
int main(int argc, char* argv[])
ViSession rm = VI NULL, vi = VI NULL;
ViStatus status;
char string[256];
ViUInt32 retCnt;
int i = 0;
bool lockflag = false;
bool bLockState = false;
if (argc == 2 && argv[1][0] == '--' && argv[1][1] == 'l') {
lockflag = true;
}
status = viOpenDefaultRM(&rm);
if (status < VI SUCCESS) goto error;
status = viOpen(rm, "GPIB8::1::INSTR", NULL, NULL, &vi);
if (status < VI SUCCESS) goto error;
for (i = 1; i < 100; i++)
if (lockflag) {
viLock(vi, VI EXCLUSIVE LOCK, VI_TMO_INFINITE,
NULL, NULL);
bLockState = true;
}
status = viWrite(vi, (ViBuf) "ch1:scale?", 10, &retCnt);
if (status < VI SUCCESS) goto error;
status = viRead(vi, (ViBuf) string, 256, &retCnt);
if (status < VI SUCCESS) goto error;
```

```
printf("%d: scale %s", i, string);
status = viWrite(vi, (ViBuf) "ch1:position?", 13, &retCnt);
if (status < VI SUCCESS) goto error;
status = viRead(vi, (ViBuf) string, 256, &retCnt);
if (status < VI SUCCESS) goto error;
printf("%d: position %s", i, string);
if (lockflag) {
viUnlock(vi);
bLockState = false;
}
}
viClose(vi);
viClose(rm);
return 0;
error:
viStatusDesc(rm, status, string);
fprintf(stderr, "Error: %s\n", (ViBuf) string);
if (bLockState && vi != VI NULL)
viUnlock(vi);
if (vi != VI NULL)
viClose(vi);
if (rm != VI NULL)
viClose(rm);
return 0:
```

Testing exclusive locking

You can see for yourself how exclusive locking works by running two instances of the program as follows:

1. Bring up an MS-DOS Prompt window, change to the directory where the EXLOCKEXAM.EXE file is located, and type:

EXLOCKEXAM -I



Note: Be sure to type I for locked, not the number 1.

- 2. Before you press Enter, bring up another MS-DOS Prompt window, change to the same directory, and type
- 3. Now press Enter in each window in quick succession.

The locked instance runs and prints correctly, while the unlocked instance exits with an error.

4. Try running the programs again with both instances having the -l lock switch, or try running them with neither having the -l lock switch, to see the possibilities.

If you run two instances with the -I option, both will run correctly. If you run two instances at once without the -I option, they will not work correctly (and will terminate with an error).

Lock sharing

Because the VISA locking mechanism is session-based, multiple threads sharing a session that has locked a resource have the same access privileges to that resource. Some applications, however, with separate sessions to a resource might want all those sessions to have the same privilege as the session that locked the resource. In other cases, there might be a need to share locks among sessions in different applications. Essentially, sessions that acquire a lock to a resource may share the lock with other sessions they select, and exclude access from other sessions.

VISA defines a shared lock type that gives exclusive access privileges to a session, along with the discretionary capability to share these exclusive privileges. A session can acquire a shared lock on a resource to get exclusive access privileges to it. When sharing the resource using a shared lock, the **viLock()** operation returns an accessKey that can be used to share the lock. The session can then share this lock with any other session by passing around the accessKey.

Before other sessions can access the locked resource, they need to acquire the lock by passing the accesskey in the requestedKey parameter of the **viLock()** operation. Invoking **viLock()** with the same key will register the new session to have the same access privilege as the original session. The session that acquired the access privileges through the sharing mechanism can also pass the access key to other sessions for resource sharing. All the sessions sharing a resource using the shared lock should synchronize their accesses to maintain a consistent state of the resource.

VISA provides the flexibility for applications to specify a key to use as the accessKey, instead of VISA generating the accessKey. Applications can suggest a key value to use through the requestedKey parameter of the **viLock()** operation. If the resource was not locked, the resource will use this requestedKey as the accessKey. If the resource was locked using a shared lock and the requestedKey matches the key with which the resource was locked, the resource will grant shared access to the session. If an application attempts to lock a resource using a shared lock and passes VI_NULL as the requestedKey parameter, VISA will generate an accessKey for the session.

A session seeking to share an exclusive lock with other sessions needs to acquire a shared lock for this purpose. If it requests an exclusive lock, no valid access key will be returned. Consequently, the session will not be able to share it with any other sessions. This precaution minimizes the possibility of inadvertent or malicious access to the resource.

Acquiring an exclusive lock while owning a shared lock

When multiple sessions have acquired a shared lock, VISA allows one of the sessions to acquire an exclusive lock along with the shared lock it is holding. That is, a session holding a shared lock could also acquire an exclusive lock using the **viLock()** operation. The session holding both the exclusive and shared lock will have the same access privileges that it had when it was holding the shared lock only. However, this would prevent other sessions holding the shared lock from accessing the locked resource. When the session holding the exclusive lock releases the resource using the **viUnlock()** operation, all the sessions (including the one that had acquired the exclusive lock) will again have all the access privileges associated with the shared lock. This is useful when multiple sessions holding a shared lock must synchronize. This can also be used when one of the sessions must execute in a critical section.

In the reverse case in which a session is holding an exclusive lock only (no shared locks), VISA does not allow it to change to a shared lock.

Nested locks

VISA supports nested locking. That is, a session can lock the same VISA resource multiple times for the same lock type. Unlocking the resource requires an equal number of invocations of the **viUnlock()** operation. A resource can be actually unlocked only when the lock count is 0.

Each session maintains a separate lock count for each type of lock. Repeated invocations of the **viLock()** operation for the same session will increase the appropriate lock count, depending on the type of lock requested. In the case of a shared lock, nesting **viLock()** calls will return with the same accessKey every time. In case of an exclusive lock, **viLock()** will not return any accessKey, regardless of whether it is nested or not.

A session does not need to pass in the access key obtained from the previous invocation of **viLock()** to gain a nested shared lock on the resource. However, if an application does pass in an access key when nesting on shared locks, it must be the correct one for that session.

SHAREDLOCK.CPP example

The following C++ example, **SHAREDLOCK.CPP**, demonstrates acquiring an exclusive lock while holding a shared lock, and also illustrates nested locking. In this example, the program opens the Default Resource Manager and opens a session to the GPIB device with primary address 1 on board 8. The program then uses the vilock() operation to establish a shared lock on the device for an infinite period

of time, with "mykey" defined as the key to the lock. A shared lock allows other applications that use the same key to have access to the specified resource. Next the program opens a FOR loop that will iterate 100 times.

Each time through the loop, the program uses the **vilock()** operation toset an exclusive lock on the device for an infinite period of time. This lock is nested inside the shared lock on the resource. The program then uses a series of **viWrite()** and **viRead()** operations to send and receive Tektronix TDS scope commands and responses as follows:

- 1. The :ch1:scale? command queries the oscilloscope for the vertical scale of channel 1. Sending this command is equivalent to selecting Vertical Setup from the Vertical menu and then viewing the Scale. The program reads the response from the scope and then prints it, along with the number of times the program has been through the FOR loop.
- 2. The :ch1:position? command queries the oscilloscope for the vetical position setting for channel 1. This command is equivalent to selecting Position from the Vertical menu.vertical Position/Scale of channel 1. The program reads the response from the scope and then prints it, along with the number of times the program has been through the FOR loop.

Each time through the loop, the program unlocks the exclusive lock on the device using the viUnlock() operation, and sleeps long enough for a cooperating program that shares the lock to execute. Once the program exits the FOR loop, it unlocks the outer shared lock on the device using the **viUnlock()** operation, closes the session to the oscilloscope, and closes the session to the Default Resource Manager.

#include <stdio.h> #include <stdlib.h> #include "visa.h" #include <windows.h> #include <signal.h> ViSession rm = VI NULL, vi = VI NULL; int main(int argc, char* argv[]) ViStatus status; char string[256]; ViUInt32 retCnt; int i = 0: status = viOpenDefaultRM(&rm); if (status < VI SUCCESS) goto error; status = viOpen(rm, "GPIB8::1::INSTR", VI NULL, VI NULL, &vi); if (status < VI SUCCESS) goto error; // A shared lock only allows other applications that use the same // key to have access to the specified resource. viLock(vi, VI SHARED LOCK, VI TMO INFINITE, "mykey", VI NULL); for (i = 1; i < 100; i++)viLock(vi, VI EXCLUSIVE LOCK, VI TMO INFINITE, VI NULL, VI NULL); status = viWrite(vi, (ViBuf) "ch1:scale?", 10, &retCnt); if (status < VI SUCCESS) goto error; status = viRead(vi, (ViBuf) string, 256, &retCnt); if (status < VI SUCCESS) goto error; printf("%d: scale %s", i, string); status = viWrite(vi, (ViBuf) "ch1:position?", 13, &retCnt); if (status < VI SUCCESS) goto error; status = viRead(vi, (ViBuf) string, 256, &retCnt); if (status < VI_SUCCESS) goto error; printf("%d: position %s", i, string); viUnlock(vi); ::Sleep(1000); } // Clean up and exit

```
viUnlock(vi);
viClose(vi);
viClose(rm);
return 0;
error:
// Print error info
viStatusDesc(rm, status, string);
fprintf(stderr, "Error: %s\n", (ViBuf) string);
// Clean up
if (vi != VI NULL) {
// clear all remaining locks
while (viUnlock(vi) >= VI SUCCESS)
viClose(vi);
}
if (rm != VI NULL)
viClose(rm);
```

Testing shared locking

You can see for yourself how shared locking works by running two instances of the program as follows:

- 1. Bring up an MS-DOS Prompt window, change to the directory where the SHAREDLOCK.EXE file is located, and type: SHAREDLOCK
- Before you press Enter, bring up another MS-DOS Prompt window, change to the same directory, and type SHAREDLOCK
- 3. Now press Enterin each window in quick succession.

The two instances with the shared lock cooperate and work together, taking turns sequentially while the other one sleeps.

4. Now try running the EXLOCKEXAM exclusive locking example with the -switch, while one or more instances of the SHAREDLOCK program are running.

The EXLOCKEXAM program will wait until all instances of the SHAREDLOCK program have completed before it can access the resource.

Building a graphical user interface

The VISAAPIDemo example incorporates a number of TekVISA operations and illustrates their use in a C++ program with a graphical user interface.




Figure 7: VISAAPIDemo graphical user interface

When the viGetAttribute/viSetAttribute... button is pressed, the following dialog box appears:

VISA Attributes	
VISA Attribute	Close
Scope: this session Access: read/write	
Get Attribute Value	
	viGetAttribute
Set Attribute Value	
ViBoolean: VI_FALSE C VI_TRUE C	viSetAttribute
ViUInt32: 1000	

When the enable I/O completion button is pressed, the following confirmation box appears:



The source code for this example can be found on your CD. The following figure illustrates the control toolbar and various windows used in building this example in Visual C++.




Figure 8: C++ Controls toolbar and form, code, and properties windows


Appendix A: VISA data type assignments

Tables A1 and A2 give the type assignments for ANSI C and Visual Basic for each generic VISA data type. Although ANSI C types can be defined in a header file, Visual Basic types cannot.

Table A1 lists those types that are both used and exported by direct users of VISA (such as instrument drivers). Table A2 lists types that may be used but not exported by such users. For example, end-users would see the types specified in A1 exported by a VXI Plug&Play instrument driver; however, end users would not see the types specified in Table A2.

Thus, if you are writing a program using the VISA API, you will see the data types in both tables. However, if you are writing a program using a VXI Plug&Play instrument driver API, you will only see the data types in Table A1.

Figure A1 shows the instrument drivers that your program can use.



Application Development Environments (ADE)

Figure 9: A1-Your program can use the instrument driver API or VISA API

Table 256: A1-Type assignments for VISA and instrument driver APIs

VISA data type	C / Visual basic bindings	Description
ViUInt32	unsigned long	An array of 32-bit unsigned integers.
	Long	
Table continued	- ·	•

VISA data type	C / Visual basic bindings	Description
ViPUInt32	ViUInt32*	The location of an array of 32-bit unsigned integers.
	N/A	
ViAUInt32	ViUInt32[]	An array of 32-bit unsigned integers.
	N/A	
Vilnt32	signed long	A 32-bit signed integers.
	Long	
ViPInt32	Vilnt32*	The location of an array of 32-bit signed integers.
	N/A	
ViAInt32	Vilnt32[]	An array of 32-bit signed integers.
	N/A	
ViUInt16	unsigned short	A 16-bit unsigned integer.
	Integer	
ViPUInt16	ViUInt16*	The location of an array of 16-bit unsigned integer.
	N/A	
ViAUInt16	ViUInt16[]	An array of 16-bit unsigned integers.
	N/A	
Vilnt16	signed short	A 16-bit signed integer.
	Integer	
ViPInt16	Vilnt16*	The location of an array of 16-bit signed integer.
	N/A	
ViAInt16	Vilnt16[]	An array of 16-bit signed integers.
	N/A	
ViUInt8	unsigned char	An 8-bit unsigned integers.
	Integer/Byte	
ViPUInt8	ViUInt8*	The location of an array of 8-bit unsigned integers.
	N/A	
ViAUInt8	ViUInt8[]	An array of 8-bit unsigned integers.
	N/A	

VISA data type	C / Visual basic bindings	Description
Vilnt8	signed char	An array of 8-bit signed integers.
	Integer/Byte	
ViPInt8	Vilnt8*	The location of an array of 8-bit signed integer.
	N/A	
ViAInt8	Vilnt8[]	An array of 8-bit signed integers.
	N/A	
ViAddr	void*	A type that references another data type, in cases where the other data
	Long	type may vary depending on a particular context.
ViPAddr	ViAddr*	The location of a ViAddr.
	N/A	
ViAAddr	ViAddr[]	An array of type ViAddr.
	N/A	
ViChar	char	An array of 8-bit integers representing an ASCII character.
	Integer/Byte	
ViPChar	ViChar*	The location of a ViChar.
	N/A	
ViAChar	ViChar[]	An array of type ViChar.
	N/A	
ViByte	unsigned char	An array 8-bit unsigned integers representing an extended ASCII character.
	Integer/Byte	
ViPByte	ViByte*	The location of a ViByte.
	N/A	
ViAByte	ViByte[]	An array of type ViByte.
	N/A	
ViBoolean	ViUInt16	A type for which there are two complementary values:
	Integer	• VI_TRUE
		• VI_FALSE
ViPBoolean	ViBoolean*	The location of a ViBoolean.
	N/A	

VISA data type	C / Visual basic bindings	Description
ViABoolean	ViBoolean[] N/A	An array of type ViBoolean.
ViReal32	float Single	A 32-bit single-precision value.
ViPReal32	ViReal32* N/A	The location of a 32-bit single-precision value.
ViAReal32	ViReal32[] N/A	An array of 32-bit single-precision values.
ViReal64	double Double	A 64-bit double-precision value.
ViPReal64	ViReal64* N/A	The location of a 64-bit double-precision value.
ViAReal64	ViReal64[] N/A	An array of 64-bit double-precision values.
ViBuf	ViPByte String	The location of a block of data.
ViPBuf	ViPByte String	The location to store a block of data.
ViABuf	ViBuf[] N/A	An array of type ViBuf.
ViString	ViPChar String	The location of a NULL-terminated ASCII string.
ViPString	ViPChar String	The location to store a NULL-terminated ASCII string.
ViAString	ViString[] N/A	An array of type ViString.
ViRsrc	ViString String	A ViString type that is further restricted to adhere to the addressing grammar for resources as described in Table 2-63.

VISA data type	C / Visual basic bindings	Description
ViPRsrc	ViString String	The location to store a ViRsrc.
ViARsrc	ViRsrc[] N/A	An array of type ViRsrc.
ViStatus	Vilnt32 Long	A defined type that contains values corresponding to VISA-defined Completion and Error termination codes.
ViPStatus	ViStatus* N/A	The location of a ViStatus.
ViAStatus	ViStatus[] N/A	An array of type ViStatus.
ViVersion	ViUInt32 Long	A defined type that contains a reference to all information necessary for the architect to represent the current version of a resource.
ViPVersion	ViVersion* N/A	The location of a ViVersion.
ViAVersion	ViVersion[] N/A	An array of type ViVersion.
ViObject	ViUInt32 Long	The most fundamental VISA data type. It contains attributes and can be closed when no longer needed.
ViPObject	ViObject* N/A	The location of a ViObject.
ViAObject	ViObject[] N/A	An array of type ViObject.
ViSession	ViObject Long	A defined type that contains a reference to all information necessary for the architect to manage a communication channel with a resource.
ViPSession	ViSession* N/A	The location of a ViSession.
ViASession	ViSession[] N/A	An array of type ViSession.

VISA data type	C / Visual basic bindings	Description
ViAttr	ViUInt32	A type that uniquely identifies an attribute.
	Long	
ViConstString	const ViChar* String	A ViString type that is guaranteed to not be modified by any driver.

Table 257: A2-Type assignments for VISA APIs only

VISA data type	C / Visual basic bindings	Description
ViAccessMode	ViUInt32 Long	A defined type that specifies the different mechanisms that control access to a resource.
ViPAccessMode	ViAccessMode* N/A	The location of a ViAccessMode.
ViBusAddress	ViUInt32 Long	A type that represents the system dependent physical address.
ViPBusAddress	ViBusAddress* N/A	The location of a ViBusAddress.
ViBusSize	ViUInt32 Long	A type that represents the system dependent physical address size.
ViAttrState	ViUInt32 Long	A value unique to the individual type of an attribute.
ViPAttrState	void* Any	The location of a ViAttrState.
ViVAList	va_list Any	The location of a list of a variable number of parameters of differing types.
ViEventType	ViUInt32 Long	A defined type that uniquely identifies the type of an event.
ViPEventType	ViEventType* N/A	The location of a ViEventType.
ViAEventType	ViEventType* N/A	An array of type ViEventType.

VISA data type	C / Visual basic bindings	Description	
ViPAttr	ViAttr*	The location of a ViAttr.	
	N/A		
ViAAttr	ViAttr*	An array of type ViAttr.	
	N/A		
ViEventFilter	ViUInt32	A defined type that specifies filtering masks or other	
	Long	information unique to an event.	
ViFindList	ViObject	A defined type that contains a reference to all resources found	
	Long	during a search operation.	
ViPFindList	ViFindList*	The location of a	
	N/A	ViFindList.	
ViEvent	ViObject	A defined type that encapsulates the information necessary to	
	Long	process an event.	
ViPEvent	ViEvent*	The location of a ViEvent.	
	N/A		
ViKeyld	ViString	A defined type that contains a reference to all information	
	String	necessary for the architect to manage the association of a thread or process and session with a lock on a resource.	
ViPKeyld	ViPString	The location of a ViKeyId.	
	String		
ViJobld	ViUInt32	A defined type that contains a reference to all information	
	Long	necessary for the architect to encapsulate the information necessary for a posted operation request.	
ViPJobld	ViJobld*	The location of a ViJobld.	
	N/A		
ViHndlr	ViStatus (*)	A value representing an entry point to an operation for use as	
	(ViSession, ViEventType, ViEvent, ViAddr)	a callback.	
	N/A		

Appendix B: Completion and error codes

The following Tektronix VISA completion and error codes are presented in alphabetical order within category.

Table 258: B1-Completion codes

Code	Description
VI_SUCCESS_DEV_NPRESENT	The session opened successfully, but the device at the specified address is not responding.
VI_SUCCESS_EVENT_EN	The specified event is already enabled for at least one of the specified mechanisms.
VI_SUCCESS_EVENT_DIS	The specified event is already disabled for at least one of the specified mechanisms.
VI_SUCCESS_MAX_CNT	The number of bytes read is equal to count.
VI_SUCCESS_NCHAIN	Event handled successfully. Do not invoke any other handlers on this session for this event.
VI_SUCCESS_NESTED_EXCLUSIVE	The specified access mode is successfully acquired, and this session has nested exclusive locks.
VI_SUCCESS_NESTED_SHARED	The specified access mode is successfully acquired, and this session has nested shared locks.
VI_SUCCESS_QUEUE_EMPTY	The operation completed successfully, but queue was empty.
VI_SUCCESS_QUEUE_NEMPTY	Wait terminated successfully on receipt of an event notification. There is still at least one more event occurrence of the type specified by inEventType available for this session.
VI_SUCCESS_SYNC	Read or write operation performed synchronously.
VI_SUCCESS_TERM_CHAR	The specified termination character was read.
VI_WARN_CONFIG_NLOADED	The specified configuration either does not exist or could not be loaded; using VISA-specified defaults instead.
VI_WARN_NSUP_ATTR_STATE	Although the specified attribute state is valid, it is not supported by this implementation.
VI_WARN_NSUP_BUF	The specified buffer is not supported.
VI_WARN_NULL_OBJECT	The specified object reference is uninitialized.
	This message is returned if the value VI_NULL is passed to it.
VI_WARN_UNKNOWN_STATUS	The status code passed to the operation could not be interpreted.

Table 259: B2-error codes

Code	Description
VI_ERROR_ALLOC	The system could not allocate a formatted I/O buffer because of insufficient system resources.
VI_ERROR_ASRL_FRAMING	A framing error occurred during transfer.
VI_ERROR_ASRL_OVERRUN	An overrun error occurred during transfer. A character was not read from the hardware before the next character arrived.
VI_ERROR_ASRL_PARITY	A parity error occurred during transfer.
VI_ERROR_ATTR_READONLY	The specified attribute is read-only.
VI_ERROR_BERR	Bus error occurred during transfer.
Table continued	

Code	Description
VI_ERROR_CLOSING_FAILED	Unable to deallocate the previously allocated data structures corresponding to this session or object reference.
VI_ERROR_HNDLR_NINSTALLED	If no handler is installed for the specified event type, the request to enable the callback mechanism for the event type returns this error code. The session cannot be enabled for the VI_HNDLR mode of the callback mechanism.
VI_ERROR_INP_PROT_VIOL	Device reported an input protocol error during transfer.
VI_ERROR_INV_ACCESS_KEY	The requestedKey value passed in is not a valid access key to the specified resource.
VI_ERROR_INV_ACC_MODE	Invalid access mode.
VI_ERROR_INV_CONTEXT	Specified event context is invalid.
VI_ERROR_INV_DEGREE	Specified degree is invalid.
VI_ERROR_INV_EVENT	Specified event type is not supported by the resource.
VI_ERROR_INV_EXPR	Invalid expression specified for search.
VI_ERROR_INV_FMT	A format specifier in the writeFmt string is invalid.
VI_ERROR_INV_HNDLR_REF	Either the specified handler reference or the user context value (or both) does not match any installed handler.
VI_ERROR_INV_JOB_ID	Specified job identifier is invalid.
	This message is returned If the operation associated with the specified jobId has already completed.
VI_ERROR_INV_LOCK_TYPE	The specified type of lock is not supported by this resource.
VI_ERROR_INV_MASK	The system cannot set the buffer for the given mask.
VI_ERROR_INV_MECH	Invalid mechanism specified.
VI_ERROR_INV_OBJECTVI_ERROR_IN V_SESSION	The given session or object reference is invalid (both are the same value).
VI_ERROR_INV_PROT	The protocol specified is invalid.
VI_ERROR_INV_RSRC_NAME	Invalid resource reference specified. Parsing error.
VI_ERROR_INV_SETUP	Some implementation-specific configuration file is corrupt or does not exist.
VI_ERROR_IO	An unknown I/O error occurred during transfer.
VI_ERROR_LIBRARY_NFOUND	A code library required by VISA could not be located or loaded.
VI_ERROR_LINE_IN_USE	The specified trigger line is currently in use.
VI_ERROR_NCIC	The interface associated with the given vi is not currently the controller in charge.
VI_ERROR_NENABLED	The session must be enabled for events of the specified type in order to receive them.
VI_ERROR_NLISTENERS	No Listeners condition is detected (both NRFD and NDAC are deasserted).
VI_ERROR_NSUP_ATTR	The specified attribute is not defined by the referenced session, event, or find list.
VI_ERROR_NSUP_ATTR_STATE	VI_ERROR_NSUP_ATTR_ STATE
VI_ERROR_NSUP_FMT	A format specifier in the writeFmt string is not supported.
VI_ERROR_NSUP_OPER	The given vi does not support this operation.
VI_ERROR_OUTP_PROT_VIOL	Device reported an output protocol error during transfer.

Appendix B: Completion and error codes

Code	Description
VI_ERROR_RAW_WR_PROT_VIOL	Violation of raw write protocol occurred during transfer.
VI_ERROR_RAW_RD_ PROT_VIOL	Violation of raw read protocol occurred during transfer.
VI_ERROR_RSRC_BUSY	The resource is valid, but VISA cannot currently access it.
VI_ERROR_RSRC_LOCKED	Specified type of lock cannot be obtained because the resource is already locked with a lock type incompatible with the lock requested
VI_ERROR_RSRC_NFOUND	There are no more matches.
VI_ERROR_SESN_NLOCKED	The current session did not have any lock on the resource.
VI_ERROR_SRQ_NOCCURRED	Service request has not been received for the session.
VI_ERROR_SYSTEM_ERROR	The VISA system failed to initialize.
VI_ERROR_TMO	Timeout expired before write operation completed.

Glossary

The following are some specialized terms used within this document.

Address

A string (or other language construct) that uniquely locates and identifies a resource. VISA defines an ASCII-based grammar that associates strings with particular physical devices or interfaces and VISA resources.

ADE

Application Development Environment

API

Application Programmers Interface. The direct interface that an end user sees when creating an application. The VISA API consists of the sum of all of the operations, attributes, and events of each of the VISA Resource Classes.

Attribute

A value within a resource that reflects a characteristic of the operational state of a resource.

Bus error

An error that signals failed access to an address. Bus errors occur with low-level accesses to memory and usually involve hardware with bus mapping capabilities. For example, non-existent memory, a non-existent register, or an incorrect device access can cause a bus error.

Communication channel

The same as **Session**. A communication path between a software element and a resource. Every communication channel in VISA is unique.

Controller

A device that can control another devices or is in the process of performing an operation on another device.

Device

An entity that receives commands from a controller. A device can be an instrument, a computer (acting in a non--controller role), or a peripheral (such as a plotter or printer). In VISA, the concept of a device is generally the logical association of several VISA resources.

GPIB (General Purpose Interface Bus)

An interconnection bus and protocol that allows you to connect multiple instruments in a network under the control of a controller. Also known as IEEE 488 bus. It transfers data with eight parallel data lines, five control lines, and three handshake lines.

Instrument

A device that accepts some form of stimulus to perform a designated task, test, or measurement function. Two common forms of stimuli are message passing and register reads and writes. Other forms include triggering or varying forms of asynchronous control.

Interface

A generic term that applies to the connection between devices and controllers. It includes the communication media and the device/ controller hardware necessary for cross-communication.

Instrument driver

Library of functions for controlling a specific instrument

IVI

Interchangeable Virtual Instrument

LabVIEW

Graphical programming ADE for Windows, Windows NT, and Sun operating systems

LabWindows/CVI

C-based ADE for the Windows and Sun operating systems

LLB

LabVIEW VI library

NI-488

National Instruments GPIB interface software

NI-VXI

National Instruments VXIbus interface software

Operation

An action defined by a resource that can be performed on a resource.

Oscilloscope

An instrument for making a graph of two factors. These are typically voltage versus time.

PnP

VXIplug&play Instrument Drivers

Process

An operating system component that shares a system's resources. A multi-process system is a computer system that allows multiple programs to run simultaneously, each in a separate process environment. A single-process system is a computer system that allows only a single program to run at a given point in time.

Register

An address location that either contains a value that is a function of the state of hardware or can be written into to cause hardware to perform a particular action or to enter a particular state. In other words, an address location that controls and/or monitors hardware.

Resource class

The definition for how to create a particular resource. In general, this is synonymous with the connotation of the word class in object-oriented architectures. For VISA Instrument Control Resource Classes, this refers to the definition for how to create a resource that controls a particular capability of a device.

Resource or resource instance

In general, this term is synonymous with the connotation of the word object in object-oriented architectures. For VISA, resource more specifically refers to a particular implementation (or instance in object-oriented terms) of a resource class. In VISA, every defined software module is a resource.

Session

The same as communication channel. A communication path between a software element and a resource. Every communication channel in VISA is unique.

SRQ

IEEE 488 Service Request. This is an asynchronous request from a remote GPIB device that requires service. A service request is essentially an interrupt from a remote device. For GPIB, this amounts to asserting the SRQ line on the GPIB.

Status byte

A byte of information returned from a remote device that shows the current state and status of the device. If the device follows IEEE 488 conventions, bit 6 of the status byte indicates if the device is currently requesting service.

TVC

TekVISA Control

Template function

Instrument driver subsystem function common to the majority of VXIplug& play instrument drivers.

Top-level example

A high-level test-oriented instrument driver function. It is typically developed from the instrument driver subsystem functions.

USB

Universal Serial Bus

Virtual instrument

A name given to the grouping of software modules (in this case, VISA resources with any associated or required hardware) to give the functionality of a traditional stand-alone instrument. Within VISA, a virtual instrument is the logical grouping of any of the VISA resources. The VISA Instrument Control Resources Organizer serves as a means to group any number of any type of VISA instrument control resources within a VISA system.

VI

LabVIEW program or Virtual Instrument

Virtual GPIB

A special type of GPIB resource that creates a software connection between the embedded instrument software and the Windows software on a Tektronix Windows-based oscilloscope, without the need for any GPIB controller hardware or cables.

VISA

Virtual Instrument Software Architecture. The architecture consists of two main VISA components: the VISA Resource Manager and the VISA Instrument Control Resources.

VISA instrument control resources

This is the name given to the part of VISA that defines all of the device-specific resource classes. VISA Instrument Control Resources encompass all defined device and interface capabilities for direct, low-level instrument control.

VISA resource manager

This is the name given to the part of VISA that manages resources. This management includes support for opening, closing, and finding resources; setting attributes, retrieving attributes, and generating events on resources; and so on.

VISA resource template

This is the name given to the part of VISA that defines the basic constraints and interface definition for the creation and use of a VISA resource. All VISA resources must derive their interface from the definition of the VISA Resource Template.