

---

# Read This First

## Tektronix Instrument Switch software download instructions

Use these instructions to download the software packages for the BSASWITCH.

1. Go to the Tektronix Web site at [www.tektronix.com](http://www.tektronix.com) to download the software packages. The software packages contain the control software, drivers, and related documentation.
2. Download the latest BERTScope software (V11.02.1886 or higher) on your BERTScope instrument and follow the online instructions.
3. Download the BSASWITCH software on a control host (BERTScope instrument or Windows PC) and follow the online instructions.

The control host should be connected to the instrument switch via USB.

4. Download the optional BSAUSB3 or BSAUSB31 Receiver Test Application Software on the Windows PC and follow the online instructions.

---

**NOTE.** *Although a BERTScope or oscilloscope can be used as the controller instead of a PC, it is not recommended.*

---

Please contact your local Tektronix representative regarding any questions or download assistance.

